



pyModis Documentation

Release 0.7.0

Luca Delucchi

July 05, 2013

CONTENTS

1	About pyModis	2
1.1	Requirements	2
1.2	How to install pyModis	2
1.3	How to report a bug	3
1.4	How to compile documentation	3
1.5	Ohloh statistics	4
2	pyModis Scripts	5
2.1	modis_download.py	6
2.2	modis_parse.py	8
2.3	modis_multiparse.py	9
2.4	modis_mosaic.py	10
2.5	modis_convert.py	11
3	Example of a full process	12
3.1	Downloading data	12
3.2	Mosaic data	12
3.3	Convert data	13
4	pyModis Library	14
4.1	pyModis Package	14
	Python Module Index	23
	Index	24

pyModis is a Free and Open Source Python based library to work with MODIS data. It offers bulk-download for user selected time ranges, mosaicking of MODIS tiles, and the reprojection from Sinusoidal to other projections, convert HDF format to other formats.

pyModis library was developed to replace old bash scripts developed by Markus Neteler to download MODIS data from NASA FTP server. It is very useful for [GIS and Remote Sensing Platform](#) of [Fondazione Edmund Mach](#) to update its large collection of MODIS data.

It has several features:

- it is very useful for downloading large numbers of MODIS HDF/XML files and for using this in a cron job for automated continuous updating; it support FTP and HTTP NASA repository
- it can parse the XML file to obtain information about the HDF files
- it can convert a HDF MODIS file to GEOTIF file using [MODIS Reprojection Tool](#)
- it can create a mosaic of several tiles using [MODIS Reprojection Tool](#) and can create the xml metadata file with the information of all tiles used in mosaic

ABOUT PYMODIS

1.1 Requirements

The only required software is [MODIS Reprojection Tool](#) to convert or mosaic MODIS HDF files.

For *download* or *parse* HDF files only standard Python modules are used by pyModis library and tools.

1.2 How to install pyModis

1.2.1 Using pip

From version 0.6.3 it is possible to install pyModis using [pip](#). You have to run the following command as administrator

```
pip install pyModis
```

If you need to update your pyModis version you have to run

```
pip install --upgrade pyModis
```

With pip it is also really simple to remove the library

```
pip uninstall pyModis
```

1.2.2 Compile from source

Installing pyModis is very simple. First you need to download pyModis source code from [github repository](#).

You can use [git](#) to download the latest code (with the whole history and so it contains all the different stable versions, from the last to the first)

```
git clone https://github.com/lucadelu/pyModis.git
```

or [download the latest stable version](#) from the repository and decompress it.

Now enter the pyModis folder and launch as administrator of your computer

```
python setup.py install
```

If the installation doesn't return any errors you should be able to use `pyModis` library from a Python console. Then, launch a your favorite Python console (I really suggest `ipython`) and digit

```
import pymodis
```

If the console doesn't return any error like this

```
ImportError: No module named pymodis
```

the `pyModis` library has been installed properly and you can use it or one of the tools distributed with `pyModis`.

1.3 How to report a bug

If you find any problems in `pyModis` library you can report it using the [issues](#) tracker of [github](#).

1.4 How to compile documentation

This documentation has been made with [Sphinx](#), so you need to install it to compile the original files to obtain different output formats.

Please enter the `docs` folder of `pyModis` source and run

```
make <target>
```

with one of the following target to obtain the desired output:

- **html**: to make standalone HTML files
- **dirhtml**: to make HTML files named `index.html` in directories
- **singlehtml**: to make a single large HTML file
- **pickle**: to make pickle files
- **json**: to make JSON files
- **htmlhelp**: to make HTML files and a HTML help project
- **qthelp**: to make HTML files and a qthelp project
- **devhelp**: to make HTML files and a Devhelp project
- **epub**: to make an epub
- **latex**: to make LaTeX files, you can set `PAPER=a4` or `PAPER=letter`
- **latexpdf**: to make LaTeX files and run them through pdflatex
- **text**: to make text files
- **man**: to make manual pages
- **texinfo**: to make Texinfo files
- **info**: to make Texinfo files and run them through `makeinfo`
- **gettext**: to make PO message catalogs
- **changes**: to make an overview of all changed/added/deprecated items

- **linkcheck**: to check all external links for integrity
- **doctest**: to run all doctests embedded in the documentation (if enabled)

1.4.1 PDF link in HTML

To insert a link to PDF file of pyModis documentation into HTML documentation (the link will be added on the sidebar) you have to compile first the PDF and after the HTML, so you need to launch:

```
make latexpdf  
make html
```

If PDF file is missing no link will be added

1.5 Ohloh statistics

For more information about pyModis please visit the [pyModis Ohloh page](#)

PYMODIS SCRIPTS

The **pyModis scripts** provide you with a complete toolkit to work with MODIS data, you can download, analyze and convert data. They are developed to work from command line and inside scripts to automatically update your MODIS files dataset.

Currently the tools are 5:

- *modis_download.py*
- *modis_parse.py*
- *modis_multiparse.py*
- *modis_mosaic.py*
- *modis_convert.py*

2.1 modis_download.py

modis_download.py is a script to download MODIS data from NASA FTP servers. It can download large amounts of data and it can be profitably used with cron jobs to receive data with a fixed delay of time.

2.1.1 Usage

```
modis_download.py [options] destination_folder
```

2.1.2 Options

-h	--help	show the help message and exit
-u	--url	http/ftp server url [default=http://e4ftl01.cr.usgs.gov]
-P	--password	password to connect only if ftp server
-U	--username	username to connect only if ftp server [default=anonymous]
-t	--tiles	string of tiles separated from comma [default=none] for all tiles
-s	--source	directory on the http/ftp [default=MOLT]
-p	--product	product name as on the http/ftp server [default=MOD11A1.005]
-D	--delta	delta of day from the first day [default=10]
-f	--firstday	the day to start download, if you want change data you have to use this format YYYY-MM-DD ([default=none] is for today)
-e	--enddaythe	day to finish download, if you want change data you have to use this format YYYY-MM-DD ([default=none] use delta option)
-x		this is useful for debugging the download [default=False]
-j		download also the jpeg files [default=False]
-O		download only one day, it set delta=1 [default=False]
-A		download all days, it useful for first download of a product. It overwrite the 'firstday' and 'endday' options [default=False]
-r		remove files with size same to zero from 'destination_folder' [default=False]

2.1.3 Examples

Download Terra LST data for a month for Europe from HTTP server

```
modis_download.py -t TODO -f 2008-01-01 -e 2008-01-31
```

Download the last 15 days of Aqua LST data

```
modis_download.py -s MOLA -p MYD11A1.005 -t TODO -D 15
```

Download all tiles of NDVI for one day (you have know the right day otherwise it download nothing)

```
modis_download.py -s TODO -f 2010-12-31 -O
```

Download Snow product from FTP server

```
modis_download.py -u ftp://n4ftl01u.ecs.nasa.gov -p mail@pymodis.com  
-s SAN/MOST -p MOD10A1.005
```

2.2 modis_parse.py

modis_parse.pys is a script to parse the XML metadata file for a MODIS tile and return the requested value. It can also write the metadata information in a text file.

2.2.1 Usage

```
modis_parse.py [options] hdf_file
```

2.2.2 Options

-h --help	show the help
-a	print all possible values of metadata
-b	print the values related to the spatial max extent
-d	print the values related to the date files
-e	print the values related to the ECSDataGranule
-i	print the input layers
-o	print the other values
-p	print the values related to platform
-q	print the values related to quality
-s	print the values related to psas
-t	print the values related to times
-w --write	write the chosen information into a file

2.2.3 Examples

Return all values of metadata

```
modis_parse.py -a FILE
```

Write all values to a file

```
modis_parse.py -a -w metadataFILE.txt FILE
```

Print spatial extent and quality

```
modis_parse.py -b -q FILE
```

2.3 modis_multiparse.py

modis_multiparse.py is a script to parse several XML metadata files for MODIS tiles. It is very useful to create XML metadata file for a mosaic.

2.3.1 Usage

```
modis_multiparse.py [options] hdf_files_list
```

2.3.2 Options

-h --help	show the help
-b	print the values related to the spatial max extent
-w --write	write the MODIS XML metadata file for MODIS mosaic

2.3.3 Examples

Print values of spatial bounding box

```
modis_multiparse.py -b FILE1 FILE2 ...
```

Write xml file to use with hdf file create by *modis_convert.py*

```
modis_multiparse.py -w FILE_mosaic.xml FILE1 FILE2 ...
```

2.4 modis_mosaic.py

modis_mosaic.py is a script to create a mosaic of several MODIS tiles in HDF format.

2.4.1 Usage

```
modis_mosaic.py [options] hdflist_file
```

2.4.2 Options

-h	--help	show the help
-m	--mrt	the path to MRT software [required]
-o	--output	the name of output file [required]
-s	--subset	a subset of product's layers. The string should be similar to: 1 0 [default: all layers]

2.4.3 Examples

Convert all the layers of several tiles:

```
modis_mosaic.py -m "/usr/local/bin/" -o FILE_mosaik FILE1 FILE2 ...
```

Convert LAYERS of several LST MODIS tiles:

```
modis_mosaic.py -s "1 0 1 0" -m "/usr/local/bin/" -o FILE_mosaik FILE1 FILE2 ...
```

2.5 modis_convert.py

modis_convert.py is a script to convert MODIS data to TIF formats and different projection reference system. It is an interface to MRT mrtmosaic software, the best application for work with HDF MODIS data.

2.5.1 Usage

```
modis_convert.py [options] hdf_file
```

2.5.2 Options

-h --help	show the help
-s --subset	a subset of product's layers. The string should be similar to: 1 0 [required]
-m --mrt	the path to MRT software [required]
-o --output	the name of output file
-g --grain	the spatial resolution of output file
-d --datum	the code of datum
-r --resampl	the type of resampling
-p --proj_parameters	a list of projection parameters
-t --proj_type	the output projection system
-u --utm	the UTM zone if projection system is UTM

Warning: You can find the supported projections in the ‘Appendix C’ of [MODIS reprojection tool user’s manual](#) and the datums at section [Datum Conversion](#) of the same manual

2.5.3 Examples

Convert LAYERS from LST MODIS data with output resolution in 250 meters with latitude and longitude reference system

```
modis_convert.py -s "1 0 1 0" -m "/usr/local/bin/" -g 250 FILE
```

Convert LAYERS from NDVI MODIS data with output resolution in 500 meters with UTM projection in the 32 zone

```
modis_convert.py -s "1 0 1 0" -m "/usr/local/bin/" -g 500 -p UTM -u 32 FILE
```

EXAMPLE OF A FULL PROCESS

In this short example you can understand how to concatenate the scripts to obtain a GeoTIFF file for each band of the chosen product.

Warning: This example is based on a Linux based system. Please if you use other OS change the paths where data will be saved

3.1 Downloading data

For first you need to obtain data, so you need to use *modis_download.py*

```
modis_download.py -f 2012-12-05 -o -t h28v05,h29v05,h28v04 /tmp
```

Warning: In this example we are working on Japan extension, so please change the name of tiles according with your region.

In this example we download data for only one day (2012-12-05) using the option “-O”.

Inside /tmp/ directory you will find a file called *listfileMOD11A1.005.txt* containing the names of files downloaded. The name of file it is related to the product that you download.

Warning: Every time that you download new files of same product it will be overwrite, so if you need it, you should rename the file

3.2 Mosaic data

At this point you need to create the mosaic of the tiles downloaded. *modis_mosaic.py* is the script to use.

```
modis_mosaic.py -m /path/to/mrt/ -o /tmp/outputfile /tmp/listfileMOD11A1.005.txt
```

Warning: /path/to/mrt/ is the directory where Modis Reprojection Tools is stored

The output of this command are *outputfile.hdf* and *outputfile.hdf.xml* inside the directory /tmp. It's reading the input files contained in *listfileMOD11A1.005.txt*

3.3 Convert data

The last part of the procedure is to convert the mosaic, from HDF format and sinusoidal projection, to GeoTIFF with several projection. You have to use *modis_convert.py*

```
modis_convert.py -s '( 1 1 1 1 1 1 1 1 1 1 )' -m /path/to/mrt/
                 -o /tmp/finalfile.tif -g 250 /tmp/outputfile.hdf
```

PYMODIS LIBRARY

pyModis library it is a Python library to work with MODIS data.

It can easily used in your application to download, analyze and convert MODIS data, it is already used by GRASS GIS in r.in.modis addons tools.

It is compose by three module:

4.1 pyModis Package

4.1.1 downmodis module: is very useful to download MODIS data from NASA FTP server

```
class pymodis.downmodis.downModis(destinationFolder,  
                                pass-  
                                word=None,           user='anonymous',  
                                url='http://e4ftl01.cr.usgs.gov', tiles=None,  
                                path='MOLT', product='MOD11A1.005', to-  
                                day=None, enddate=None, delta=10, jpg=False,  
                                debug=False)
```

A class to download MODIS data from NASA FTP repository

checkDataExist (listNewFile, move=0)

Check if a file already exists in the directory of download

listNewFile = list of all files, returned by getFilesList function

move = it is useful to know if a function is called from download or move function

closeFTP ()

Close ftp connection

closeFilelist ()

Function to close the file where write the downloaded files

connect (ncon=20)

Connect to the server and fill the dirData variable

ncon = number maximum of test to connection at the server

dayDownload (day, listFilesDown)

Downloads tiles are in files_hdf_consider

listFilesDown = list of the files to download, returned by checkDataExist function

debugDays ()
This function is useful to debug the number of days

debugLog ()
Function to create the debug file

debugMaps ()
This function is useful to debug the number of maps to download for each day

downloadFile (filDown, filHdf, day)
Download the single file
filDown = name of the file to download
filSave = name of the file to write
day = the day in format YYYY.MM.DD

downloadsAllDay (clean=False, allDays=False)
Download the single file
filDown = name of the file to download
filSave = name of the file to write

getAllDays ()
Return a list of all days

getFilesList (day=None)
Create a list of files to download, it is possible choose to download also the jpeg files or only the hdf files
day = the date of data

getListDays ()
Return a list of all selected days

removeEmptyFiles ()
Check if some file has size ugual 0

setDirectoryIn (day)
Enter in the directory of the day

setDirectoryOver ()
Come back to old path

pymodis.downmodis.**getNewerVersion (oldFile, newFile)**
Return newer version of a file
oldFile = one of the two similar file
newFile = one of the two similar file

class pymodis.downmodis.modisHtmlParser (fh)
Bases: `HTMLParser.HTMLParser`
A class to parse HTML

get_all ()
Return everything

get_dates ()
Return a list of directories with date

```

get_tiles(prod, tiles, jpeg=False)
    Return a list of file to download

handle_starttag(tag, attrs)

pymodis.downmodis.str2date(strin)
    Return a date object from a string

    string = text string to return date (2012-10-04)

pymodis.downmodis.urljoin(*args)
    Joins given arguments into a url. Trailing but not leading slashes are stripped for each argument.
    http://stackoverflow.com/a/11326230

```

4.1.2 parsemodis module: is very simple library to parse MODIS metadata file, it can also write the XML metadata file for a mosaic.

```

class pymodis.parsemodis.parseModis(filename)
    Class to parse MODIS xml files, it also can create the parameter configuration file for resampling
    MODIS DATA with the MRT software or convertmodis Module

confResample(spectral, res=None, output=None, datum='WGS84', resam-
    ple='NEAREST_NEIGHBOR', projtype='GEO', utm=None, proj-
    par='( 0.0 0.0 0.0 0.0 0.0 0.0 0.0 0.0 0.0 0.0 0.0 0.0 0.0 0.0 0.0 )',
    bound=None)
    Create the parameter file to use with resample MRT software to create tif file

    spectral = the spectral subset to be used, look the product table to understand the layer that
    you want use. For example:
        •NDVI ( 1 1 1 0 0 0 0 0 0 0 0 0 ) copy only layer NDVI, EVI and QA VI the other layers
            are not used
        •LST ( 1 1 0 0 1 1 0 0 0 0 0 0 ) copy only layer daily and nightly temperature and QA

    res = the resolution for the output file, it must be set in the map unit of output projection
    system. The software will use the original resolution of input file if res it isn't set

    output = the output name, if it doesn't set will use the prefix name of input hdf file

    utm = the UTM zone if projection system is UTM

resample = the type of resampling, the valid values are:
    • NN (nearest neighbor)
    • BI (bilinear)
    • CC (cubic convolution)

projtype = the output projection system, the valid values are:
    • AEA (Albers Equal Area)
    • ER (Equirectangular)
    • GEO (Geographic Latitude/Longitude)
    • HAM (Hammer)
    • ISIN (Integerized Sinusoidal)

```

- IGH (Interrupted Goode Homolosine)
 - LA (Lambert Azimuthal)
 - LCC (LambertConformal Conic)
 - MERCAT (Mercator)
 - MOL (Mollweide)
 - PS (Polar Stereographic)
 - SIN (Sinusoidal)
 - UTM (Universal TransverseMercator)

datum = the datum to use, the valid values are:

- NAD27
 - NAD83
 - WGS66
 - WGS76
 - WGS84
 - NODATUM

projpar = a list of projection parameters, for more info check the Appendix C of MODIS reprojection tool user manual https://lpdaac.usgs.gov/content/download/4831/22895/file/mrt41_usermanual_032811.pdf

bound = dictionary with the following keys:

- max_lat
 - max_lon
 - min_lat
 - min_lon

```
confResample_swath(sds, geoloc, res, output=None, sphere='8', resample='NN',  
    projtype='GEO', utm=None, projpar='0.0 0.0 0.0 0.0 0.0 0.0 0.0 0.0  
    0.0 0.0 0.0 0.0 0.0 0.0 0.0 0.0 0.0 0.0', bound=None)
```

Create the parameter file to use with resample MRT software to create tif file

sds = Name of band/s (Science Data Set) to resample

`geoloc` = Name geolocation file (example MOD3, MYD3)

`res` = the resolution for the output file, it must be set in the map unit of output projection system. The software will use the original resolution of input file if `res` isn't set

`output` = the output name, if it doesn't set will use the prefix name of input hdf file

sphere = Output sphere number. Valid options are:

- 0=Clarke 1866
 - 1=Clarke 1880
 - 2=Bessel

- 3=International 1967
- 4=International 1909
- 5=WGS 72
- 6=Everest
- 7=WGS 66
- 8=GRS1980/WGS 84
- 9=Airy
- 10=Modified Everest
- 11=Modified Airy
- 12=Walbeck
- 13=Southeast Asia
- 14=Australian National
- 15=Krassovsky
- 16=Hough
- 17=Mercury1960
- 18=Modified Mercury1968
- 19=Sphere 19 (Radius 6370997)
- 20=MODIS Sphere (Radius 6371007.181)

resample = the type of resampling, the valid values are:

- NN (nearest neighbor)
- BI (bilinear)
- CC (cubic convolution)

projtype = the output projection system, the valid values are:

- AEA (Albers Equal Area)
- ER (Equirectangular)
- GEO (Geographic Latitude/Longitude)
- HAM (Hammer)
- ISIN (Integerized Sinusoidal)
- IGH (Interrupted Goode Homolosine)
- LA (Lambert Azimuthal)
- LCC (LambertConformal Conic)
- MERCAT (Mercator)
- MOL (Mollweide)
- PS (Polar Stereographic),

- SIN ()Sinusoidal)
- UTM (Universal TransverseMercator)

utm = the UTM zone if projection system is UTM

projpar = a list of projection parameters, for more info check the Appendix C of MODIS reprojection tool user manual
https://lpdaac.usgs.gov/content/download/4831/22895/file/mrt41_usermanual_032811.pdf

bound = dictionary with the following keys:

- max_lat
- max_lon
- min_lat
- min_lon

getGranule()

Set the GranuleURMetaData element

getRoot()

Set the root element

retBoundary()

Return the maximum extend (Bounding Box) of the MODIS file as dictionary

retBrowseProduct()

Return the BrowseProduct element

retCollectionMetaData()

Return the CollectionMetaData element as dictionary

retDTD()

Return the DTDVersion element

retDataCenter()

Return the DataCenterId element

retDataFiles()

Return the DataFiles element as dictionary

retDataGranule()

Return the ECSDataGranule elements as dictionary

retDbID()

Return the DbID element

retGranuleUR()

Return the GranuleUR element

retInputGranule()

Return the input files (InputGranule) used to process the considered file

retInsertTime()

Return the InsertTime element

retLastUpdate()

Return the LastUpdate element

retMeasure()
Return statistics of QA as dictionary

retPGEVersion()
Return the PGEVersion element

retPSA()
Return the PSA values as dictionary, the PSAName is the key and and PSAValue is the value

retPlatform()
Return the platform values as dictionary.

retRangeTime()
Return the RangeDateTime elements as dictionary

class `pymodis.parsemodis.parseModisMulti(hdflist)`
A class to obtain some variables for the xml file of several MODIS tiles. It can also create the xml file

valBound()
Function return the Bounding Box of mosaic

valCollectionMetaDataSet(obj)
Function to add CollectionMetaData

obj = element to add CollectionMetaData

valDTD(obj)
Function to add DTDVersion

obj = element to add DTDVersion

valDataCenter(obj)
Function to add DataCenter

obj = element to add DataCenter

valDataFiles(obj)
Function to add DataFileContainer

obj = element to add DataFileContainer

valDbID(obj)
Function to add DbID

obj = element to add DbID

valGranuleUR(obj)
Function to add GranuleUR

obj = element to add GranuleUR

valInputPointer(obj)
Function to add InputPointer

obj = element to add InputPointer

valInsertTime(obj)
Function to add the minimum of InsertTime

obj = element to add InsertTime

valMeasuredParameter (obj)
Function to add ParameterName
obj = element to add ParameterName

valPGEVersion (obj)
Function to add PGEVersion
obj = element to add PGEVersion

valPlatform (obj)
Function to add Platform elements
obj = element to add Platform elements

valRangeTime (obj)
Function to add RangeDateTime
obj = element to add RangeDateTime

writexml (outputname)
Write a xml file for a mosaic
outputname = the name of xml file

4.1.3 convertmodis module: using MRT software, can convert MODIS HDF file to GeoTiff file or create a HDF mosaic file for several tiles.

```
class pymodis.convertmodis.convertModis (hdfname, confile, mrtpath)
A class to convert modis data from hdf to tif using resample (from MRT tools)

executable ()
Return the executable of resample MRT software

run ()
Exec the conversion process

class pymodis.convertmodis.createMosaic (listfile, outprefix, mrtpath, sub-
set=False)
A class to convert several MODIS tiles into a mosaic

executable ()
Return the executable of mrtmosaic MRT software

run ()
Exec the mosaic process

write_mosaic_xml ()
Write the XML metadata file for MODIS mosaic

class pymodis.convertmodis.processModis (hdfname, confile, mrtpath, in-
puthdf=None, outputhdf=None, ge-
ologfile=None)
A class to process raw modis data from hdf to tif using swath2grid (from MRT Swath tools)

executable ()
Return the executable of resample MRT software

run ()
Exec the conversion process
```

We acknowledge the [Fondazione Edmund Mach](#) for promoting the development of free and open source software.

PYTHON MODULE INDEX

p

`pymodis.convertmodis`, 21
`pymodis.downmodis`, 14
`pymodis.parsemodis`, 16

INDEX

C

checkDataExist() (pymodis.downmodis.downModis method), 14
closeFilelist() (pymodis.downmodis.downModis method), 14
closeFTP() (pymodis.downmodis.downModis method), 14
confResample() (pymodis.parsemodis.parseModis method), 16
confResample_swath() (pymodis.parsemodis.parseModis method), 17
connect() (pymodis.downmodis.downModis method), 14
convertModis (class in pymodis.convertmodis), 21
createMosaic (class in pymodis.convertmodis), 21

D

dayDownload() (pymodis.downmodis.downModis method), 14
debugDays() (pymodis.downmodis.downModis method), 14
debugLog() (pymodis.downmodis.downModis method), 15
debugMaps() (pymodis.downmodis.downModis method), 15
downloadFile() (pymodis.downmodis.downModis method), 15
downloadsAllDay() (pymodis.downmodis.downModis method), 15
downModis (class in pymodis.downmodis), 14

E

executable() (pymodis.convertmodis.convertModis method), 21
executable() (pymodis.convertmodis.createMosaic method), 21

executable() (pymodis.convertmodis.processModis method), 21

G

get_all() (pymodis.downmodis.modisHtmlParser method), 15
get_dates() (pymodis.downmodis.modisHtmlParser method), 15
get_tiles() (pymodis.downmodis.modisHtmlParser method), 15
getAllDays() (pymodis.downmodis.downModis method), 15
getFilesList() (pymodis.downmodis.downModis method), 15
getGranule() (pymodis.parsemodis.parseModis method), 19
getListDays() (pymodis.downmodis.downModis method), 15
getNewerVersion() (in module pymodis.downmodis), 15
getRoot() (pymodis.parsemodis.parseModis method), 19

H

handle_starttag() (pymodis.downmodis.modisHtmlParser method), 16

M

modisHtmlParser (class in pymodis.downmodis), 15

P

parseModis (class in pymodis.parsemodis), 16
parseModisMulti (class in pymodis.parsemodis), 20
processModis (class in pymodis.convertmodis), 21
pymodis.convertmodis (module), 21
pymodis.downmodis (module), 14
pymodis.parsemodis (module), 16

R

removeEmptyFiles() (py-modis.downmodis.downModis method), 15
retBoundary() (pymodis.parsemodis.parseModis method), 19
retBrowseProduct() (py-modis.parsemodis.parseModis method), 19
retCollectionMetaData() (py-modis.parsemodis.parseModis method), 19
retDataCenter() (pymodis.parsemodis.parseModis method), 19
retDataFiles() (pymodis.parsemodis.parseModis method), 19
retDataGranule() (py-modis.parsemodis.parseModis method), 19
retDbID() (pymodis.parsemodis.parseModis method), 19
retDTD() (pymodis.parsemodis.parseModis method), 19
retGranuleUR() (pymodis.parsemodis.parseModis method), 19
retInputGranule() (py-modis.parsemodis.parseModis method), 19
retInsertTime() (pymodis.parsemodis.parseModis method), 19
retLastUpdate() (pymodis.parsemodis.parseModis method), 19
retMeasure() (pymodis.parsemodis.parseModis method), 19
retPGEVersion() (py-modis.parsemodis.parseModis method), 20
retPlatform() (pymodis.parsemodis.parseModis method), 20
retPSA() (pymodis.parsemodis.parseModis method), 20
retRangeTime() (pymodis.parsemodis.parseModis method), 20
run() (pymodis.convertmodis.convertModis method), 21
run() (pymodis.convertmodis.createMosaic method), 21
run() (pymodis.convertmodis.processModis method), 21

S

setDirectoryIn() (py-modis.downmodis.downModis method), 15
setDirectoryOver() (py-modis.downmodis.downModis method), 15
str2date() (in module pymodis.downmodis), 16
U
urljoin() (in module pymodis.downmodis), 16
V
valBound() (pymodis.parsemodis.parseModisMulti method), 20
valCollectionMetaData() (py-modis.parsemodis.parseModisMulti method), 20
valDataCenter() (py-modis.parsemodis.parseModisMulti method), 20
valDataFiles() (py-modis.parsemodis.parseModisMulti method), 20
valDbID() (pymodis.parsemodis.parseModisMulti method), 20
valDTD() (pymodis.parsemodis.parseModisMulti method), 20
valGranuleUR() (py-modis.parsemodis.parseModisMulti method), 20
valInputPointer() (py-modis.parsemodis.parseModisMulti method), 20
valInsTime() (py-modis.parsemodis.parseModisMulti method), 20
valMeasuredParameter() (py-modis.parsemodis.parseModisMulti method), 20
valPGEVersion() (py-modis.parsemodis.parseModisMulti method), 21
valPlatform() (py-modis.parsemodis.parseModisMulti method), 21
valRangeTime() (py-modis.parsemodis.parseModisMulti method), 21
W
write_mosaic_xml() (py-

modis.convertmodis.createMosaic
method), 21
writexml() (pymodis.parsemodis.parseModisMulti
method), 21