

---

# **auxi User Manual**

***Release 0.3.0rc1***

**Ex Mente Technologies (Pty) Ltd.**

**Jul 21, 2016**



## CONTENTS

<b>1</b>	<b>Introduction</b>	<b>1</b>
<b>2</b>	<b>Getting Started</b>	<b>3</b>
2.1	auxi Installation . . . . .	3
2.2	Importing auxi Components . . . . .	3
2.3	Getting Help . . . . .	4
<b>3</b>	<b>Structure</b>	<b>5</b>
3.1	Tools . . . . .	5
3.2	Modelling Frameworks . . . . .	19
<b>4</b>	<b>auxi Reference</b>	<b>57</b>
4.1	auxi package . . . . .	57
<b>5</b>	<b>Indices and tables</b>	<b>125</b>
	<b>Python Module Index</b>	<b>127</b>
	<b>Index</b>	<b>129</b>



## INTRODUCTION

auxi is a toolkit to help metallurgical process engineers with their day-to-day tasks. Many of the calculations that we do require things like molar masses, conversion of one compound to another using stoichiometry, heat transfer calculations, mass balances, energy balances, etc. It is usually quite time consuming to get started with these calculations in a tool like Excel. auxi aims to save you time by making many of these calculations available from within python.

We hope that auxi will help you spend less time focusing on searching for formulas and data, and setting up calculations, and more on thinking about the problems that you need to solve with these calculations. Enjoy!

For video tutorials on using auxi visit [auxi youtube](#) .



## GETTING STARTED

### 2.1 auxi Installation

auxi runs on both Linux and Windows.

#### 2.1.1 Prerequisite

NumPy is required to run the auxi.modelling.materials packages. You can follow the instructions at <http://www.scipy.org/install.html> on how to install NumPy.

#### 2.1.2 Installation

To install auxi:

```
* On Linux: sudo pip install auxi
* On Windows: pip install auxi
```

To uninstall auxi:

```
* On Linux: sudo pip uninstall auxi
* On Windows: pip uninstall auxi
```

### 2.2 Importing auxi Components

If you want to use auxi in one of your python modules, you need to import its components in the same way that you do for any other python package. For example, to use the stoichiometry tool, you will have to do the following:

```
from auxi.tools.chemistry import stoichiometry
```

The same method is used for all modules, functions and classes in auxi. Here are a few more import examples:

```
from auxi.tools.chemistry.stoichiometry import molar_mass
from auxi.tools.chemistry.stoichiometry import molar_mass as mm
from auxi.tools.chemistry.stoichiometry import convert_compound
from auxi.tools.chemistry.stoichiometry import convert_compound as _
↪ CC

from auxi.tools.chemistry import thermochemistry
from auxi.tools.chemistry.thermochemistry import Compound
```

## 2.3 Getting Help

You can use Python's standard help function on any of auxi's components. For example:

```
import auxi
help(auxi)

from auxi.tools.chemistry import stoichiometry

help(stoichiometry)
help(stoichiometry.molar_mass)
help(stoichiometry.convert_compound)
```

All the help information that you are able to access in this way are also available through auxi's HTML documentation that is included in the auxi Python package distribution.



## STRUCTURE

auxi is a Python package, and it is currently divided into two main sub-packages, namely tools and modelling. The tools package provides help with simple tasks like calculating molar masses, enthalpies of heat capacities. The modelling package helps you to do more sophisticated calculations, and to build process models.

### 3.1 Tools

This package currently only contains a single set of tools, namely for chemistry calculations.

#### 3.1.1 Chemistry Tools

The `auxi.tools.chemistry` package contains modules, functions and classes for doing chemical calculations. Specifically, the package contains a module called “stoichiometry” for doing stoichiometry calculations, and another called “thermochemistry” for doing thermochemical calculations.

#### 3.1.2 Chemical Calculations

The `auxi.tools.chemistry` sub-package provides you with modules, classes and functions to do chemical calculations. The calculations are divided into the categories of stoichiometry and thermochemistry.

##### Stoichiometry Calculations

##### Warning

`auxi.tools.chemistry.stoichiometry` is not yet able to successfully parse compound formulae that contain parentheses. It is therefore suggested that a formula such as “Fe2(SO4)3” rather be expressed as “Fe2S3O12”.

## Calculating Molar Mass

Determining the molar mass of a substance is done countless times in mass and energy balance models and other process models. It usually requires you to create your own little database or list that you look up the values from. Once you have that, you can perform the required calculations. The `auxi.tools.chemistry.stoichiometry` module provides the `molar_mass()` function for this purpose.

### Standard Approach

The normal way of getting the molar mass of one or more compounds is as follows:

```
from auxi.tools.chemistry import stoichiometry

molarmass_FeO = stoichiometry.molar_mass("FeO")
molarmass_CO2 = stoichiometry.molar_mass("CO2")
molarmass_FeCr2O4 = stoichiometry.molar_mass("FeCr2O4")

print("Molar mass of FeO      :", molarmass_FeO, "kg/kmol")
print("Molar mass of CO2      :", molarmass_CO2, "kg/kmol")
print("Molar mass of FeCr2O4:", molarmass_FeCr2O4, "kg/kmol")
```

The result of this should be:

```
Molar mass of FeO      : 71.8444 kg/kmol
Molar mass of CO2      : 44.0095 kg/kmol
Molar mass of FeCr2O4: 223.8348 kg/kmol
```

### Compact Approach

One of Python's strengths is its ability to make code very compact. You may not always want to use a lengthy "`stoichiometry.molar_mass`" reference to the function. Rather than importing the `stoichiometry` module, we can import the `molar_mass()` function directly, and give it another name. Here is how you can make it short and sweet:

```
from auxi.tools.chemistry.stoichiometry import molar_mass as mm

molarmass_FeO = mm("FeO")

print("Molar mass of FeO      :", molarmass_FeO, "kg/kmol")
print("Molar mass of CO2      :", mm("CO2"), "kg/kmol")
print("Molar mass of FeCr2O4:", mm("FeCr2O4"), "kg/kmol")
```

The result is still the same:

```
Molar mass of FeO      : 71.8444 kg/kmol
Molar mass of CO2      : 44.0095 kg/kmol
Molar mass of FeCr2O4: 223.8348 kg/kmol
```

## More Examples

Here are some more examples of molar mass calculations:

```
from auxi.tools.chemistry.stoichiometry import molar_mass as mm

def print_molar_mass(compound):
    print("Molar mass of", compound, "is", mm(compound), "kg/kmol.")

print_molar_mass("FeO1.5")
print_molar_mass("Fe2O3")
print_molar_mass("FeOTiO2")
print_molar_mass("FeTiO3")
print_molar_mass("Fe2(CO3)3")
print_molar_mass("Fe2C3O9")
print_molar_mass("H2O")
print_molar_mass("H")
print_molar_mass("He")
print_molar_mass("Au")
```

And the results are:

```
Molar mass of FeO1.5 is 79.8441 kg/kmol.
Molar mass of Fe2O3 is 159.6882 kg/kmol.
Molar mass of FeOTiO2 is 151.7102 kg/kmol.
Molar mass of FeTiO3 is 151.7102 kg/kmol.
Molar mass of Fe2(CO3)3 is 291.7167 kg/kmol.
Molar mass of Fe2C3O9 is 291.7167 kg/kmol.
Molar mass of H2O is 18.01528 kg/kmol.
Molar mass of H is 1.00794 kg/kmol.
Molar mass of He is 4.002602 kg/kmol.
Molar mass of Au is 196.96655 kg/kmol.
```

## Calculating Compound Amount

Sometimes you need to convert the mass of a compound (kg) to the equivalent amount (kmol). The `stoichiometry` module provides the `amount()` function to do this.

The amount is calculated as follows:

$$n_{\text{compound}} = \frac{m_{\text{compound}}}{mm_{\text{compound}}}$$

where

- $n_{\text{compound}}$  is the compound amount in kmol.
- $m_{\text{compound}}$  is the compound mass in kg.

- $mm_{\text{compound}}$  is the compound molar mass in kg/kmol.

## Standard Approach

The normal way of calculating the amount of a compound is as follows:

```
from auxi.tools.chemistry import stoichiometry

m_FeO = 10.0
n_FeO = stoichiometry.amount("FeO", m_FeO)
print("There is", n_FeO, "kmol of FeO in", m_FeO , "kg of the_
↳compound.")

m_CO2 = 12.3
n_CO2 = stoichiometry.amount("CO2", m_CO2)
print("There is", n_CO2, "kmol of CO2 in", m_CO2 , "kg of the_
↳compound.")

m_FeCr2O4 = 453.0
n_FeCr2O4 = stoichiometry.amount("FeCr2O4", m_FeCr2O4)
print("There is", n_FeCr2O4, "kmol of FeCr2O4 in",
      m_FeCr2O4 , "kg of the compound.")
```

The result of this should be:

```
There is 0.1391896932815919 kmol of FeO in 10.0 kg of the compound.
There is 0.2794851111691794 kmol of CO2 in 12.3 kg of the compound.
There is 2.0238139913900786 kmol of FeCr2O4 in 453.0 kg of the_
↳compound.
```

## Compact Approach

To make the code more compact, we can import the function instead of the module and get the same result like this:

```
from auxi.tools.chemistry.stoichiometry import amount

m_FeO = 10.0
n_FeO = amount("FeO", m_FeO)
print("There is", n_FeO, "kmol of FeO in", m_FeO , "kg of the_
↳compound.")

m_CO2 = 12.3
n_CO2 = amount("CO2", m_CO2)
print("There is", n_CO2, "kmol of CO2 in", m_CO2 , "kg of the_
↳compound.")

m_FeCr2O4 = 453.0
```

```
n_FeCr2O4 = amount("FeCr2O4", m_FeCr2O4)
print("There is", n_FeCr2O4, "kmol of FeCr2O4 in",
      m_FeCr2O4 , "kg of the compound.")
```

The result is still the same:

```
There is 0.1391896932815919 kmol of FeO in 10.0 kg of the compound.
There is 0.2794851111691794 kmol of CO2 in 12.3 kg of the compound.
There is 2.0238139913900786 kmol of FeCr2O4 in 453.0 kg of the
↳ compound.
```

## Calculating Compound Mass

You often have the amount (kmol) of a compound and then need to calculate its mass. The `stoichiometry` module provides the `mass()` function for this. The mass is calculate with this formula:

$$m_{\text{compound}} = n_{\text{compound}} \cdot mm_{\text{compound}}$$

where

- $m_{\text{compound}}$  is the compound mass in kg.
- $n_{\text{compound}}$  is the compound amount in kmol.
- $mm_{\text{compound}}$  is the compound molar mass in kg/kmol.

From this point forward the standard and compact approaches are not both demonstrated. Only the standard method, which imports the module, is used below since it is more explicit:

```
from auxi.tools.chemistry import stoichiometry

n_FeO = 10.0
m_FeO = stoichiometry.mass("FeO", n_FeO)
print("There is", m_FeO, "kg of FeO in", n_FeO , "kmol of the
↳ compound.")

m_CO2 = 12.3
n_CO2 = stoichiometry.mass("CO2", m_CO2)
print("There is", m_CO2, "kg of CO2 in", n_CO2 , "kmol of the
↳ compound.")

m_FeCr2O4 = 453.0
n_FeCr2O4 = stoichiometry.mass("FeCr2O4", m_FeCr2O4)
print("There is", m_FeCr2O4, "kg of FeCr2O4 in",
      n_FeCr2O4 , "kmol of the compound.")
```

The results are:

```
There is 718.444 kg of FeO in 10.0 kmol of the compound.  
There is 12.3 kg of CO2 in 541.31685 kmol of the compound.  
There is 453.0 kg of FeCr2O4 in 101397.1644 kmol of the compound.
```

## Identifying Elements in Compounds

The list of elements present in one or more compounds can be used when calculating element balances. Determining this list is often done manually. `stoichiometry` has the `elements()` function to automate this task. This is how you use it:

```
from auxi.tools.chemistry import stoichiometry

elements_Fe2O3 = stoichiometry.elements(["Fe2O3"])
print("Fe2O3 contains these elements:", elements_Fe2O3)

elements_CO2 = stoichiometry.elements(["CO2"])
print("CO2 contains these elements:", elements_CO2)

elements_Fe2Cr2O4 = stoichiometry.elements(["Fe2Cr2O4"])
print("Fe2Cr2O4 contains these elements:", elements_Fe2Cr2O4)

elements_Al2S3O12 = stoichiometry.elements(["Al2(SO4)3"])
print("Al2(SO4)3 contains these elements:", elements_Al2S3O12)

elements_all = stoichiometry.elements(["Fe2O3", "CO2", "Fe2Cr2O4",
    ↪ "Al2(SO4)3"])
print("Fe2O3, CO2, Fe2Cr2O4 and Al2(SO4)3 contain these elements:",
    elements_all)
```

Here are the results:

```
Fe2O3 contains these elements: {'Fe', 'O'}
CO2 contains these elements: {'O', 'C'}
Fe2Cr2O4 contains these elements: {'Fe', 'O', 'Cr'}
Al2(SO4)3 contains these elements: {'Al', 'O', 'S'}
Fe2O3, CO2, Fe2Cr2O4 and Al2(SO4)3 contain these elements:
    {'Al', 'Fe', 'O', 'C', 'S', 'Cr'}
```

## Calculating Stoichiometry Coefficients

The `stoichiometry_coefficient()` and `stoichiometry_coefficients()` functions in `stoichiometry` determine the stoichiometry coefficients of elements in chemical compounds automatically. If we are only interested in the coefficient for a single element, we use `stoichiometry_coefficient()` like this:

```
from auxi.tools.chemistry import stoichiometry
```

```

coeff_Fe2O3_Fe = stoichiometry.stoichiometry_coefficient("Fe2O3",
↪ "Fe")
print("Stoichiometry coefficient of Fe in Fe2O3:", coeff_Fe2O3_Fe)

coeff_Fe2O3_O = stoichiometry.stoichiometry_coefficient("Fe2O3", "O
↪ ")
print("Stoichiometry coefficient of O in Fe2O3:", coeff_Fe2O3_O)

coeff_Fe2O3_C = stoichiometry.stoichiometry_coefficient("Fe2O3", "C
↪ ")
print("Stoichiometry coefficient of C in Fe2O3:", coeff_Fe2O3_C)

```

The results are:

```

Stoichiometry coefficient of Fe in Fe2O3: 2.0
Stoichiometry coefficient of O in Fe2O3: 3.0
Stoichiometry coefficient of C in Fe2O3: 0.0

```

We can determine the coefficients for a list of elements using the `stoichiometry_coefficients()` function:

```

from auxi.tools.chemistry import stoichiometry

elements = ["Fe", "O", "C", "Ar"]
st_Fe2O3 = stoichiometry.stoichiometry_coefficients("Fe2O3", ↪
↪ elements)
print("Stoichiometry coefficient of", elements, "in Fe2O3:",
      st_Fe2O3)

elements = ["Al", "Ca", "Fe", "Si", "O", "C", "H"]
st_Lawsonite = stoichiometry.stoichiometry_coefficients(
↪ "CaAl2Si2O7(OH)2·H2O",
                                                    elements)
print("Stoichiometry coefficient of", elements,
      "in Lawsonite (CaAl2(Si2O7)(OH)2·H2O):", st_Lawsonite)

```

This produces these results:

```

Stoichiometry coefficient of ['Fe', 'O', 'C', 'Ar'] in Fe2O3:
[2.0, 3.0, 0.0, 0.0]
Stoichiometry coefficient of ['Al', 'Ca', 'Fe', 'Si', 'O', 'C', 'H']
in Lawsonite (CaAl2(Si2O7)(OH)2·H2O):
[2.0, 1.0, 0.0, 2.0, 10.0, 0.0, 4.0]

```

## Calculating Element Mass Fractions

Another two useful tools in the calculation of element balances are the `element_mass_fraction()` and `element_mass_fractions()` functions in `stoichiometry`. They are similar to the stoichiometry coefficient functions, but calculate

the mass fraction of an element or list of elements in a chemical compound. The calculations are done with the following equation:

$$y_{\text{compound,element}} = \frac{n_{\text{compound,element}} \cdot mm_{\text{element}}}{mm_{\text{compound}}}$$

where

- $y_{\text{compound,element}}$  is the mass fraction of the specified element in the compound.
- $n_{\text{compound,element}}$  is the stoichiometry coefficient of the specified element in the compound.
- $mm_{\text{element}}$  is the element's molar mass in kg/kmol.
- $mm_{\text{compound}}$  is the compound's molar mass in kg/kmol.

For determining the mass fraction of a single element we can use `element_mass_fraction()` as follows:

```
from auxi.tools.chemistry import stoichiometry

y_Fe2O3_Fe = stoichiometry.element_mass_fraction("Fe2O3", "Fe")
print("Mass fraction of Fe in Fe2O3:", y_Fe2O3_Fe)

y_Fe2O3_O = stoichiometry.element_mass_fraction("Fe2O3", "O")
print("Mass fraction of O in Fe2O3:", y_Fe2O3_O)

y_Fe2O3_C = stoichiometry.element_mass_fraction("Fe2O3", "C")
print("Mass fraction of C in Fe2O3:", y_Fe2O3_C)
```

This produces these results:

```
Mass fraction of Fe in Fe2O3: 0.699425505453753
Mass fraction of O in Fe2O3: 0.300574494546247
Mass fraction of C in Fe2O3: 0.0
```

Similarly, we can use `element_mass_fractions()` to perform the calculation for a list of elements:

```
from auxi.tools.chemistry import stoichiometry

elements = ["Fe", "O", "C", "Ar"]
y_Fe2O3 = stoichiometry.element_mass_fractions("Fe2O3", elements)
print("Mass fractions of", elements, "in Fe2O3:", y_Fe2O3)

elements = ["Al", "Ca", "Fe", "Si", "O", "C", "H"]
y_Lawsonite = stoichiometry.element_mass_fractions(
    "CaAl2Si2O7O2H2H2O", elements)
print("Mass fractions of", elements,
      "in Lawsonite (CaAl2(Si2O7)(OH)2·H2O):",
      y_Lawsonite)
```

This results in:



```

Mass fractions of ['Fe', 'O', 'C', 'Ar'] in Fe2O3:
[ 0.69942551  0.30057449  0.0  0.0 ]
Mass fractions of ['Al', 'Ca', 'Fe', 'Si', 'O', 'C', 'H']
in Lawsonite (CaAl2(Si2O7)(OH)2·H2O):
[ 0.17172686  0.12754034  0.0  0.17875314  0.50914938  0.0  0.
↪01283028 ]

```

## Converting Compounds

Sometimes it is needed to convert the mass of one compound to an equivalent mass of another compound. For example, how much Fe will I get when I reduce a certain mass of Fe<sub>2</sub>O<sub>3</sub>? stoichiometry has the `convert_compound()` function to help out. The function calculates the result as follows:

$$m_{\text{target}} = m_{\text{source}} \cdot \frac{y_{\text{source,element}}}{y_{\text{target,element}}}$$

where

- $m_{\text{target}}$  is the target compound mass in kg.
- $m_{\text{source}}$  is the source compound mass in kg.
- $y_{\text{target,element}}$  is the mass fraction of the specified base element in the target compound.
- $y_{\text{source,element}}$  is the mass fraction of the specified base element in the source compound.

Here are some simple examples of how to use `convert_compound()` :

```

from auxi.tools.chemistry import stoichiometry

m_Fe2O3 = 10.0
m_Fe = stoichiometry.convert_compound(m_Fe2O3, "Fe2O3", "Fe", "Fe")
print("From", m_Fe2O3, "kg of Fe2O3,", m_Fe ,
      "kg of Fe can be produced.")

m_Fe = 10.0
m_Fe2O3 = stoichiometry.convert_compound(m_Fe, "Fe", "Fe2O3", "Fe")
print("When", m_Fe, "kg of Fe is oxidised completely,", m_Fe2O3 ,
      "kg of Fe2O3 will be produced.")

```

The results are:

```

From 10.0 kg of Fe2O3, 6.994255054537531 kg of Fe can be produced.
When 10.0 kg of Fe is oxidised completely, 14.297448294386246 kg of
Fe2O3 will be produced.

```

## Thermochemical Calculations

### Preparing Thermochemical Data

The `auxi.tools.chemistry.thermochemistry` module provides a number of useful functions for doing thermochemical calculations that would otherwise have been quite cumbersome to do. To make these calculations possible, some thermochemical data is needed. The *auxi* distribution package currently contains data for around 80 compounds. This may, however, not be sufficient for your process calculations. FactSage data can be converted into auxi thermochemical data using the `convert_fact_file_to_auxi_thermo_file()` function.

To prepare your own compound data files with FactSage, follow these steps:

- Open FactSage.
- Click on the “View Data” button.
- Select the “Compound” option, NOT “Solution”.
- Select the database that you want to use. “FactPS” should be OK.
- Type the formula of the compound you need in the box at the bottom.
- Click OK.
- Click on the “Cp(T)” tab.
- Select “File” from the menu and then “Save As ...”.
- Select the folder where you want to store all your thermochemical data files.
- The filename must have a specific format. Taking “Ar” as an example, use “Compound\_Ar.txt” for the file name.
- Click “Save”.

You will have to repeat this procedure for all the compounds that you need to include in your calculations.

To convert the factsage file to an auxi thermochemical file use the following code:

```
from auxi.tools.chemistry import thermochemistry as thermo

thermo.convert_fact_file_to_auxi_thermo_file("path/to/factsage_file
→", "path/to/new_auxi_thermo_file")
```

### Loading Thermochemical Data

If you are going to use the default set of data provided with *auxi*, you do not need to do anything. The entire data set will be available by default. You can obtain a list of all the compounds and their phases by using the following code:

```
from auxi.tools.chemistry import thermochemistry as thermo

thermo.list_compounds()
```

Here are the first few lines of the result:

```
Compounds currently loaded in the thermochemistry module:
Ag ['G', 'L', 'S']
Ag2O ['S']
Al ['G', 'L', 'S']
Al2O3 ['G', 'L', 'S1', 'S2', 'S3', 'S4']
Al4C3 ['S1']
C ['G', 'S1', 'S2']
C2H2 ['G']
CH4 ['Aq', 'G']
CO ['G']
CO2 ['G']
...
```

The result lists all the compounds with the phases for which data are available. Taking the compound SiO<sub>2</sub> as an example, data are available for eight solid phases (S1 to S8), for the liquid phase and for the gas phase.

If you have decided to create your own data folder, you can force *auxi* to use the data in that folder. Here is the code for this:

```
from auxi.tools.chemistry import thermochemistry as thermo

thermo.load_data('/home/someuser/thermodata')
thermo.list_compounds()
```

This example data folder only contains a small selection of files:

```
Compounds currently loaded in the thermo module:
Ag ['G', 'L', 'S']
CaO ['G', 'L', 'S']
Cr2O3 ['L', 'S']
Cu ['G', 'L', 'S']
CuO ['G', 'S']
```

## Calculating Heat Capacity

The `Cp()` function in the `auxi.tools.chemistry.thermochemistry` module can be used to calculate the heat capacity at constant pressure for a compound. This can be done as follows:

```
from auxi.tools.chemistry import thermochemistry as thermo

Cp_H2O = thermo.Cp("H2O[L]", 70.0)
```

```
print("The Cp of 1 kg of water at 70 °C is", Cp_H2O, "kWh/K.")

Cp_H2O = thermo.Cp("H2O[G]", 70.0)
print("The Cp of 1 kg of water vapour at 70 °C is", Cp_H2O, "kWh/K.
↳")

m_ZrO2 = 2.34
Cp_ZrO2 = thermo.Cp("ZrO2[S1]", 893.5, m_ZrO2)
print("The Cp of 2.34 kg of ZrO2[S1] at 893.5 °C is", Cp_ZrO2, "kWh/
↳K.")
```

Here are the results:

```
The Cp of 1 kg of water at 70 °C is 0.0011634065724223574 kWh/K.
The Cp of 1 kg of water vapour at 70 °C is 0.0005217114220395267
↳kWh/K.
The Cp of 2.34 kg of ZrO2[S1] at 70 °C is 0.0004084615851157184 kWh/
↳K.
```

The first parameter to the function must specify both the compound's formula and phase. If the phase is not specified it is impossible to calculate a result. The heat capacity of water is clearly significantly different from that of water vapour.

The last parameter of the `Cp()` is mass and it is optional. If no value is specified, it is taken to be 1 kg. This was the case for the first two calculations above. A mass of 2.34 kg was specified in the last `Cp` calculation.

## Calculating Enthalpy

The `H()` function in `thermochemistry` is used to calculate the enthalpy of a compound. This can be done as follows:

```
from auxi.tools.chemistry import thermochemistry as thermo

H_H2O = thermo.H("H2O[L]", 70.0)
print("The enthalpy of 1 kg of water at 70 °C is", H_H2O, "kWh.")

H_H2O = thermo.H("H2O[G]", 70.0)
print("The enthalpy of 1 kg of water vapour at 70 °C is", H_H2O,
↳"kWh.")

m_ZrO2 = 2.34
H_ZrO2 = thermo.H("ZrO2[S1]", 893.5, m_ZrO2)
print("The enthalpy of 2.34 kg of ZrO2[S1] at 893.5 °C is", H_ZrO2,
↳"kWh.")
```

Here are the results:

```
The enthalpy of 1 kg of water at 70 °C is -4.35495670039936 kWh.
The enthalpy of 1 kg of water vapour at 70 °C is -3.
↳7054553712406264 kWh.
The enthalpy of 2.34 kg of ZrO2[S1] at 893.5 °C is -5.
↳463105585819936 kWh.
```

The parameters to the `H()` function works the same as that of the `Cp()` function. Both formula and phase are required in the first parameter, the second is temperature in °C and the third is mass, which is optional with a default value of 1 kg.

## Calculating Entropy

The `S()` function in `thermochemistry` is used to calculate the entropy of a compound. This can be done as follows:

```
from auxi.tools.chemistry import thermochemistry as thermo

S_H2O = thermo.S("H2O[L]", 70.0)
print("The entropy of 1 kg of water at 70 °C is", S_H2O, "kWh/K.")

S_H2O = thermo.S("H2O[G]", 70.0)
print("The entropy of 1 kg of water vapour at 70 °C is", S_H2O,
      ↳"kWh/K.")

m_ZrO2 = 2.34
S_ZrO2 = thermo.S("ZrO2[S1]", 893.5, m_ZrO2)
print("The entropy of 2.34 kg of ZrO2[S1] at 893.5 °C is", S_ZrO2,
      ↳"kWh/K.")
```

Here are the results:

```
The entropy of 1 kg of water at 70 °C is 0.0012418035680941087 kWh/
↳K.
The entropy of 1 kg of water vapour at 70 °C is 0.
↳0029829908763826032 kWh/K.
The entropy of 2.34 kg of ZrO2[S1] at 893.5 °C is 0.
↳000762164298048799 kWh/K.
```

The parameters to the `S()` function works the same as that of the `Cp()` function. Both formula and phase are required in the first parameter, the second is temperature in °C and the third is mass, which is optional with a default value of 1 kg.

## Calculating Gibbs Free Energy

The `G()` function in `thermochemistry` is used to calculate the Gibbs free energy of a compound. This can be done as follows:

```
from auxi.tools.chemistry import thermochemistry as thermo

G_H2O = thermo.G("H2O[L]", 70.0)
print("The Gibbs free energy of 1 kg of water at 70 °C is", G_H2O,
      "kWh.")

G_H2O = thermo.G("H2O[G]", 70.0)
print("The Gibbs free energy of 1 kg of water vapour at 70 °C is",
      ↪G_H2O,
      "kWh.")

m_ZrO2 = 2.34
G_ZrO2 = thermo.G("ZrO2[S1]", 893.5, m_ZrO2)
print("The Gibbs free energy of 2.34 kg of ZrO2[S1] at 893.5 °C is
      ↪", G_ZrO2,
      "kWh.")
```

Here are the results:

```
The Gibbs free energy of 1 kg of water at 70 °C is
-4.781081594790853 kWh.
The Gibbs free energy of 1 kg of water vapour at 70 °C is
-4.729068690471317 kWh.
The Gibbs free energy of 2.34 kg of ZrO2[S1] at 893.5 °C is
-6.352284564138569 kWh.
```

The parameters to the `G()` function works the same as that of the `Cp()` function. Both formula and phase are required in the first parameter, the second is temperature in °C and the third is mass, which is optional with a default value of 1 kg.

### 3.1.3 Material Physical Properties Tools

The `auxi.tools.transportphenomena` package provides tools to calculate material physical properties.

### 3.1.4 Transport Phenomena Tools

The `auxi.tools.transportphenomena` package provides tools to do calculations related to heat transfer, mass transfer, and fluid flow.

### 3.1.5 Heat transfer Calculations

The `auxi.tools.transportphenomena` sub-package provides tools to do calculations related to heat transfer.

## 3.2 Modelling Frameworks

This package contains modules, functions and classes for developing different types of computational models.

### 3.2.1 Process Modelling

The `auxi.modelling.process` package contains modules, functions and classes for performing process modelling. Specifically, the package contains a module called “materials” for modelling materials.

#### Material Modelling

The `auxi.modelling.process` sub-package provides you with modules, classes and functions to model process. The process modelling package contains material models.

#### Material Modelling

The `auxi.modelling.process.materials` package contains modules, functions and classes that help perform material-related calculations and build process models. Specifically, the package contains a module called “chemistry” for a material and material package that can perform chemistry calculations, another called “psd” for a particulate material and material package that can do size distribution as well as a material and material package that can, in addition, perform slurry calculations, and another called “thermochemistry” that contains a material consisting of multiple chemical compounds, having the ability to do thermochemical calculations.

#### Material Models

The `auxi.modelling.process.materials` sub-package provides you with modules, classes and functions to do material modelling. The material models are divided into chemical, psd and thermochemistry.

#### Concepts

#### Motivation

The material, material assay and material package concepts used in `auxi.modelling.process.materials` may initially seem somewhat foreign to new users. These concepts were developed to assist process engineers when doing metallurgical calculations, and while developing process models. It aims to reduce the complexity and time involved in performing these important but sometimes tedious tasks. Once these concepts have been mastered, they become incredibly powerful in the hands of a metallurgical process engineer.

## Materials, Material Assays and Material Packages

`auxi.modelling.process.materials` includes a number of different representations of materials, material assays and material packages, each of which is contained in a separate Python module. The different modules cater for different situations as follows:

- `auxi.modelling.process.materials.psd` describes materials using particle size distributions. It can be used for processes in which particle size is the most important material property, such as a comminution circuit.
- `auxi.modelling.process.materials.slurry` adds water to `psd`. It can describe the solid and liquid portion of a particulate process such as a comminution circuit.
- `auxi.modelling.process.materials.chem` can be used for doing mass balances in chemically reactive processes such as leaching, precipitation, direct reduction and smelting. Its material class describes a material using its chemical composition. This module cannot perform any energy balance calculations.
- `auxi.modelling.process.materials.thermo` adds thermochemistry to `chem`. It can be used to do mass and energy balances in chemically reactive system such as smelting furnaces, direct reduction kilns, etc.

The `auxi.modelling.process.materials.thermo` module will be used to illustrate the concepts here.

### Material

A `Material` class is used to represent a “type of material”. Examples are ilmenite, iron ore, coal, ferrochrome alloy, etc. These terms are fairly abstract and generic, since they don’t refer to something specific. The `thermo` module’s `Material` class uses a list of specific phases of chemical compounds to describe a “type of material”. Here are some examples:

=====	=====
Material	Material
=====	=====
Name                      Ilmenite	Name                      Coal
-----	-----
Compound	Compound
-----	-----
Al2O3[S1]	C[S1]
CaO[S]	H2[G]
Cr2O3[S]	O2[G]
Fe2O3[S1]	N2[G]
Fe3O4[S1]	S[S1]
FeO[S]	Al2O3[S1]
K2O[S]	CaO[S]
MgO[S]	Fe2O3[S1]
MnO[S]	MgO[S]
Na2O[S1]	SiO2[S1]



```

P4O10[S]
SiO2[S1]
TiO2[S1]
V2O5[S]
=====

```

With the Ilmenite material we are specifying that, in our model or calculation, ilmenites will consist of the 14 compounds included in the first list. In the case of Coal, different coals will consist of the 10 compounds listed in the second list.

## Material Assay

When we need to develop a model or do some calculations, it is not sufficient to simply know that a “type of material”, such as ilmenite or coal, can consist of a specified list of compound phases. We need to know what the composition of a “specific material” is. With this composition we will be able to get started on some calculations. This is where material assays come in. In the next example, assays were added to the two materials defined above:

```

=====
Material
=====
Name                Ilmenite
-----
Composition Details (mass fractions)
Compound            IlmeniteA            IlmeniteB            IlmeniteC
-----
Al2O3[S1]            1.16000000e-02        1.55000000e-02        9.41000000e-03
CaO[S]               2.20000000e-04        1.00000000e-05        1.70000000e-04
Cr2O3[S]             8.00000000e-05        2.20000000e-04        1.10000000e-04
Fe2O3[S1]            2.02000000e-01        4.73000000e-01        4.96740000e-01
Fe3O4[S1]            0.00000000e+00        0.00000000e+00        0.00000000e+00
FeO[S]               2.79000000e-01        1.91000000e-01        0.00000000e+00
K2O[S]               4.00000000e-05        1.00000000e-05        5.00000000e-05
MgO[S]               1.04000000e-02        5.80000000e-03        1.09000000e-02
MnO[S]               5.40000000e-03        4.80000000e-03        5.25000000e-03
Na2O[S1]             7.00000000e-05        5.00000000e-05        3.10000000e-04
P4O10[S]             1.00000000e-05        3.20000000e-04        1.50000000e-04
SiO2[S1]             8.50000000e-03        4.90000000e-03        1.74400000e-02
TiO2[S1]             4.77000000e-01        2.94000000e-01        4.59490000e-01
V2O5[S]              3.60000000e-03        8.00000000e-03        0.00000000e+00
=====

=====
Material
=====
Name                Coal
-----
Composition Details (mass fractions)

```

Compound	ReductantA	ReductantB
C[S1]	8.40973866e-01	1.00000000e+00
H2[G]	1.37955186e-02	0.00000000e+00
O2[G]	4.94339606e-02	0.00000000e+00
N2[G]	6.09802120e-03	0.00000000e+00
S[S1]	2.04933390e-03	0.00000000e+00
Al2O3[S1]	1.20884160e-03	0.00000000e+00
CaO[S]	2.94179980e-03	0.00000000e+00
Fe2O3[S1]	7.85955656e-02	0.00000000e+00
MgO[S]	1.41179360e-03	0.00000000e+00
SiO2[S1]	3.49129950e-03	0.00000000e+00
=====		

Our Ilmenite material now has three assays associated with it, and they are named IlmeniteA, IlmeniteB and IlmeniteC. Ilmenite therefore refers to a “type of material”, and IlmeniteA, IlmeniteB and IlmeniteC refer to “specific materials”.

Two assays were added to our Coal material. The first, ReductantA, refers to a coal with 84 % carbon and roughly 8.5 % ash. Reductant B is pure graphite.

## Material Packages

Using `auxi.modelling.process` we can now create a certain quantity of a “specific material” that is identified by a material and material assay. When we do this with the `thermo.Material` class, we also have to specify pressure and temperature. The result of creating 1000 kg of IlmeniteB at 1 atm pressure and 500 °C temperature is the following:

=====			
MaterialPackage			
=====			
Material	Ilmenite		
Mass	1.00000000e+03	kg	
Amount	9.81797715e+00	kmol	
Pressure	1.00000000e+00	atm	
Temperature	5.00000000e+02	°C	
Enthalpy	-1.87069549e+03	kWh	
-----			
Compound Details:			
Formula	Mass	Mass Fraction	Mole Fraction
-----			
Al2O3[S1]	1.55371337e+01	1.55371337e-02	1.55207829e-02
CaO[S]	1.00239573e-02	1.00239573e-05	1.82066196e-05
Cr2O3[S]	2.20527060e-01	2.20527060e-04	1.47782739e-04
Fe2O3[S1]	4.74133178e+02	4.74133178e-01	3.02416515e-01
Fe3O4[S1]	0.00000000e+00	0.00000000e+00	0.00000000e+00
FeO[S]	1.91457584e+02	1.91457584e-01	2.71429867e-01
K2O[S]	1.00239573e-02	1.00239573e-05	1.08388880e-05
MgO[S]	5.81389521e+00	5.81389521e-03	1.46923993e-02

MnO[S]	4.81149948e+00	4.81149948e-03	6.90848565e-03
Na2O[S1]	5.01197863e-02	5.01197863e-05	8.23650657e-05
P4O10[S]	3.20766632e-01	3.20766632e-04	1.15084949e-04
SiO2[S1]	4.91173906e+00	4.91173906e-03	8.32630400e-03
TiO2[S1]	2.94704343e+02	2.94704343e-01	3.75840583e-01
V2O5[S]	8.01916581e+00	8.01916581e-03	4.49078466e-03
=====			

In the above result some of the useful work that `auxi.modelling.process.materials` does behind the scenes is already evident. The amount in kmol and the enthalpy in kWh of the material package was calculated, as were the masses and mole fractions of the compounds. You will notice that the mass fractions in the material package is slightly different from those in the IlmeniteB material assay. This is because the assay was automatically normalised to add up to 1.0. You can switch of normalisation if that is more appropriate.

## Summary

The `auxi.modelling.process.materials` concepts described above can be summarised as follows:

- A material provides a list of properties that describes a “type of material”.
- A material assay describes a “specific material” by providing values for the listed properties.
- A material package describes a “specific quantity of material” belonging to a certain “type of material”.

You may be wondering what the use of all this is. Why go through all the effort of defining materials, material assays and material packages? The next section demonstrates the power of these concepts.

## Material Package Calculations

The use of materials and material packages are demonstrated here through the use of code snippets and the results produce by that code. We will be using ilmenite in the example. Firstly, let us import the `:py:class:'auxi.modelling.process.materials.thermo.Material'` class, create a material object and print it out:

```
from auxi.modelling.process.materials.thermo import Material

ilmenite = Material("Ilmenite", "./materials/ilmenite.txt")
print(ilmenite)
```

The material looks as follows:

```
=====
Material
=====
```

Name	Ilmenite		
-----			
Composition Details	(mass fractions)		
Compound	IlmeniteA	IlmeniteB	IlmeniteC
-----			
Al2O3[S1]	1.16000000e-02	1.55000000e-02	9.41000000e-03
CaO[S]	2.20000000e-04	1.00000000e-05	1.70000000e-04
Cr2O3[S]	8.00000000e-05	2.20000000e-04	1.10000000e-04
Fe2O3[S1]	2.02000000e-01	4.73000000e-01	4.96740000e-01
Fe3O4[S1]	0.00000000e+00	0.00000000e+00	0.00000000e+00
FeO[S]	2.79000000e-01	1.91000000e-01	0.00000000e+00
K2O[S]	4.00000000e-05	1.00000000e-05	5.00000000e-05
MgO[S]	1.04000000e-02	5.80000000e-03	1.09000000e-02
MnO[S]	5.40000000e-03	4.80000000e-03	5.25000000e-03
Na2O[S1]	7.00000000e-05	5.00000000e-05	3.10000000e-04
P4O10[S]	1.00000000e-05	3.20000000e-04	1.50000000e-04
SiO2[S1]	8.50000000e-03	4.90000000e-03	1.74400000e-02
TiO2[S1]	4.77000000e-01	2.94000000e-01	4.59490000e-01
V2O5[S]	3.60000000e-03	8.00000000e-03	0.00000000e+00
=====			

## Creating, Adding and Extracting

Next we can use the material object (called `ilmenite`) to create a material package using each of the `ilmenite` assays:

```
ilma_package = ilmenite.create_package("IlmeniteA", 300.0, 1.0, 25.
↪0)
print(ilma_package)
ilmb_package = ilmenite.create_package("IlmeniteB", 500.0, 1.0, 750.
↪0)
print(ilmb_package)
ilmc_package = ilmenite.create_package("IlmeniteC", 250.0, 1.0, 1200.0)
↪1200.0)
print(ilmc_package)
```

Different masses were created from each assay (300 kg of `IlmeniteA`, 500.0 kg of `IlmeniteB` and 250.0 kg of `IlmeniteC`). All three packages were assigned a pressure of 1 atm, which is of no consequence. The packages were assigned temperatures of 25, 750 and 1200 °C respectively. In three short lines of code, `auxi.modelling.process.materials` did the following for us:

- Normalise the specified assay so that the mass fractions add up to 1.0. (We can choose not to do this.)
- Calculate the mass of each compound by multiplying the component mass fraction by the total package mass.
- Calculate the mass fraction of each compound.

- Calculate the mole fraction of each compound.
- Calculate the total amount (in kmol) of components in the package.
- Calculate the total enthalpy of the package by calculating the enthalpy of each compound and adding it together.

The result is as follows:

=====			
MaterialPackage			
=====			
Material	Ilmenite		
Mass	3.00000000e+02	kg	
Amount	3.52817004e+00	kmol	
Pressure	1.00000000e+00	atm	
Temperature	2.50000000e+01	°C	
Enthalpy	-6.87812118e+02	kWh	
-----			
Compound Details			
Formula	Mass	Mass Fraction	Mole Fraction
-----			
Al2O3[S1]	3.48725349e+00	1.16241783e-02	9.69390473e-03
CaO[S]	6.61375661e-02	2.20458554e-04	3.34280337e-04
Cr2O3[S]	2.40500241e-02	8.01667468e-05	4.48486990e-05
Fe2O3[S1]	6.07263107e+01	2.02421036e-01	1.07784066e-01
Fe3O4[S1]	0.00000000e+00	0.00000000e+00	0.00000000e+00
FeO[S]	8.38744589e+01	2.79581530e-01	3.30892788e-01
K2O[S]	1.20250120e-02	4.00833734e-05	3.61829148e-05
MgO[S]	3.12650313e+00	1.04216771e-02	2.19865404e-02
MnO[S]	1.62337662e+00	5.41125541e-03	6.48625791e-03
Na2O[S1]	2.10437710e-02	7.01459035e-05	9.62343053e-05
P4O10[S]	3.00625301e-03	1.00208434e-05	3.00142421e-06
SiO2[S1]	2.55531506e+00	8.51771685e-03	1.20540764e-02
TiO2[S1]	1.43398268e+02	4.77994228e-01	5.08901291e-01
V2O5[S]	1.08225108e+00	3.60750361e-03	1.68652807e-03
=====			
=====			
MaterialPackage			
=====			
Material	Ilmenite		
Mass	5.00000000e+02	kg	
Amount	4.90898858e+00	kmol	
Pressure	1.00000000e+00	atm	
Temperature	7.50000000e+02	°C	
Enthalpy	-9.05451326e+02	kWh	
-----			
Compound Details			
Formula	Mass	Mass Fraction	Mole Fraction
-----			
Al2O3[S1]	7.76856687e+00	1.55371337e-02	1.55207829e-02

CaO[S]	5.01197863e-03	1.00239573e-05	1.82066196e-05
Cr2O3[S]	1.10263530e-01	2.20527060e-04	1.47782739e-04
Fe2O3[S1]	2.37066589e+02	4.74133178e-01	3.02416515e-01
Fe3O4[S1]	0.00000000e+00	0.00000000e+00	0.00000000e+00
FeO[S]	9.57287918e+01	1.91457584e-01	2.71429867e-01
K2O[S]	5.01197863e-03	1.00239573e-05	1.08388880e-05
MgO[S]	2.90694760e+00	5.81389521e-03	1.46923993e-02
MnO[S]	2.40574974e+00	4.81149948e-03	6.90848565e-03
Na2O[S1]	2.50598931e-02	5.01197863e-05	8.23650657e-05
P4O10[S]	1.60383316e-01	3.20766632e-04	1.15084949e-04
SiO2[S1]	2.45586953e+00	4.91173906e-03	8.32630400e-03
TiO2[S1]	1.47352172e+02	2.94704343e-01	3.75840583e-01
V2O5[S]	4.00958290e+00	8.01916581e-03	4.49078466e-03

#### MaterialPackage

Material	Ilmenite
Mass	2.50000000e+02 kg
Amount	2.40014670e+00 kmol
Pressure	1.00000000e+00 atm
Temperature	1.20000000e+03 °C
Enthalpy	-5.25247309e+02 kWh

#### Compound Details

Formula	Mass	Mass Fraction	Mole Fraction
Al2O3[S1]	2.35245295e+00	9.40981180e-03	9.61275553e-03
CaO[S]	4.24991500e-02	1.69996600e-04	3.15758164e-04
Cr2O3[S]	2.74994500e-02	1.09997800e-04	7.53824179e-05
Fe2O3[S1]	1.24182516e+02	4.96730065e-01	3.24003606e-01
Fe3O4[S1]	0.00000000e+00	0.00000000e+00	0.00000000e+00
FeO[S]	0.00000000e+00	0.00000000e+00	0.00000000e+00
K2O[S]	1.24997500e-02	4.99990000e-05	5.52880254e-05
MgO[S]	2.72494550e+00	1.08997820e-02	2.81687499e-02
MnO[S]	1.31247375e+00	5.24989500e-03	7.70863128e-03
Na2O[S1]	7.74984500e-02	3.09993800e-04	5.20968045e-04
P4O10[S]	3.74992500e-02	1.49997000e-04	5.50346434e-05
SiO2[S1]	4.35991280e+00	1.74396512e-02	3.02328445e-02
TiO2[S1]	1.14870203e+02	4.59480810e-01	5.99250982e-01
V2O5[S]	0.00000000e+00	0.00000000e+00	0.00000000e+00

We can now add these three packages of ilmenite together:

```
total_package = ilma_package + ilmb_package + ilmc_package
print(total_package)
```

In one line of code we did the following:

- Calculate the total mass of each component by adding up the component masses from the three original packages.
- Calculate the mass fraction of each compound.
- Calculate the mole fraction of each compound.
- Calculate the total amount (in kmol) of compounds in the package.
- Calculate the total enthalpy of the package by adding up the enthalpies from the three original packages.
- Calculate the temperature of the new package.

This new package (total\_package) looks like this:

```
=====
MaterialPackage
=====
Material          Ilmenite
Mass              1.05000000e+03 kg
Amount            1.08373053e+01 kmol
Pressure          1.00000000e+00 atm
Temperature       6.61513374e+02 °C
Enthalpy          -2.11851075e+03 kWh
-----
Compound Details
Formula           Mass           Mass Fraction   Mole Fraction
-----
Al2O3[S1]         1.36082733e+01   1.29602603e-02   1.23153413e-02
CaO[S]            1.13648695e-01   1.08236852e-04   1.87005885e-04
Cr2O3[S]          1.61813004e-01   1.54107623e-04   9.82371950e-05
Fe2O3[S1]         4.21975416e+02   4.01881349e-01   2.43833300e-01
Fe3O4[S1]         0.00000000e+00   0.00000000e+00   0.00000000e+00
FeO[S]            1.79603251e+02   1.71050715e-01   2.30674699e-01
K2O[S]            2.95367407e-02   2.81302292e-05   2.89340215e-05
MgO[S]            8.75839623e+00   8.34132975e-03   2.00516825e-02
MnO[S]            5.34160012e+00   5.08723821e-03   6.94823498e-03
Na2O[S1]          1.23602114e-01   1.17716299e-04   1.84018059e-04
P4O10[S]          2.00888819e-01   1.91322685e-04   6.52958859e-05
SiO2[S1]          9.37109739e+00   8.92485465e-03   1.43915687e-02
TiO2[S1]          4.05620643e+02   3.86305374e-01   4.68638424e-01
V2O5[S]           5.09183399e+00   4.84936570e-03   2.58325918e-03
=====
```

We can easily extract a part of a material package into a new one. Let us remove 30 kg from the new package and store it in a new package:

```
dust_package = total_package.extract(30.0)
print(dust_package)
print(total_package)
```

By using one line of code we subtracted 30 kg of material from the original package and created a new one containing the subtracted 30 kg. All the other properties (e.g component masses, total

amount and enthalpy) of the two packages were also recalculated. The extracted 30 kg package looks like this:

=====			
MaterialPackage			
=====			
Material	Ilmenite		
Mass	3.00000000e+01	kg	
Amount	3.09637295e-01	kmol	
Pressure	1.00000000e+00	atm	
Temperature	6.61513374e+02	°C	
Enthalpy	-6.05288787e+01	kWh	
-----			
Compound Details			
Formula	Mass	Mass Fraction	Mole Fraction
-----			
Al2O3[S1]	3.88807809e-01	1.29602603e-02	1.23153413e-02
CaO[S]	3.24710557e-03	1.08236852e-04	1.87005885e-04
Cr2O3[S]	4.62322868e-03	1.54107623e-04	9.82371950e-05
Fe2O3[S1]	1.20564405e+01	4.01881349e-01	2.43833300e-01
Fe3O4[S1]	0.00000000e+00	0.00000000e+00	0.00000000e+00
FeO[S]	5.13152145e+00	1.71050715e-01	2.30674699e-01
K2O[S]	8.43906876e-04	2.81302292e-05	2.89340215e-05
MgO[S]	2.50239892e-01	8.34132975e-03	2.00516825e-02
MnO[S]	1.52617146e-01	5.08723821e-03	6.94823498e-03
Na2O[S1]	3.53148898e-03	1.17716299e-04	1.84018059e-04
P4O10[S]	5.73968055e-03	1.91322685e-04	6.52958859e-05
SiO2[S1]	2.67745640e-01	8.92485465e-03	1.43915687e-02
TiO2[S1]	1.15891612e+01	3.86305374e-01	4.68638424e-01
V2O5[S]	1.45480971e-01	4.84936570e-03	2.58325918e-03
=====			

The original package, which now contains 30 kg less, now looks like this:

=====			
MaterialPackage			
=====			
Material	Ilmenite		
Mass	1.02000000e+03	kg	
Amount	1.05276680e+01	kmol	
Pressure	1.00000000e+00	atm	
Temperature	6.61513374e+02	°C	
Enthalpy	-2.05798187e+03	kWh	
-----			
Compound Details			
Formula	Mass	Mass Fraction	Mole Fraction
-----			
Al2O3[S1]	1.32194655e+01	1.29602603e-02	1.23153413e-02
CaO[S]	1.10401589e-01	1.08236852e-04	1.87005885e-04
Cr2O3[S]	1.57189775e-01	1.54107623e-04	9.82371950e-05
Fe2O3[S1]	4.09918976e+02	4.01881349e-01	2.43833300e-01



Fe3O4 [S1]	0.00000000e+00	0.00000000e+00	0.00000000e+00
FeO [S]	1.74471729e+02	1.71050715e-01	2.30674699e-01
K2O [S]	2.86928338e-02	2.81302292e-05	2.89340215e-05
MgO [S]	8.50815634e+00	8.34132975e-03	2.00516825e-02
MnO [S]	5.18898297e+00	5.08723821e-03	6.94823498e-03
Na2O [S1]	1.20070625e-01	1.17716299e-04	1.84018059e-04
P4O10 [S]	1.95149139e-01	1.91322685e-04	6.52958859e-05
SiO2 [S1]	9.10335175e+00	8.92485465e-03	1.43915687e-02
TiO2 [S1]	3.94031481e+02	3.86305374e-01	4.68638424e-01
V2O5 [S]	4.94635301e+00	4.84936570e-03	2.58325918e-03
=====			

## Summary

All the other capabilities of the `auxi.modelling.process.materials.thermomaterial.Material` class are not demonstrated here, since the purpose of this section is simply to introduce you to the material, material assay and material package concepts in `auxi.modelling.process.materials`. For full details on how to use the different Material and MaterialPackage classes and objects, refer to the following section:

- `section_chemistry_material_calculations`
- `section_psd_material_calculations`
- `section_psd_slurry_material_calculations`
- *thermochemistry material Calculations*

The final point to make is that the classes in `auxi.modelling.process.materials` can assist you in performing large numbers of metallurgical calculations with very few lines of code. The purpose of this is to focus you on the process concepts rather than entangle you in the detail of tens or hundreds of stoichiometry and thermochemical calculations. This should keep your code clean and your mind clear, getting the job done well in a short space of time.

## thermochemistry material Calculations

The purpose of this section is to explain a number of concepts and demonstrate the use of the Material and MaterialPackage classes in the `auxi.modelling.process.materials.thermo` module.

## Material Description Files

You need to create one or more material description files (MDFs) before you can create a material object in Python. Material description data are stored in simple text files with ".txt" extensions. The most simple format of such a file is the "mix.txt" file shown here:

```
Compound
Al2O3[S1]
C[S1]
CaO[S]
Cr2O3[S]
Fe2O3[S1]
Fe3O4[S1]
FeO[S]
H2[G]
K2O[S]
MgO[S]
MnO[S]
Na2O[S1]
N2[G]
O2[G]
P4O10[S]
S[S1]
SiO2[S1]
TiO2[S1]
V2O5[S]
```

The file contains a header row, which in this case only contains the word “Compound”. All subsequent rows contain chemical compound phases. For example, the second line contains the S1 phase of Al<sub>2</sub>O<sub>3</sub>. When you consult FactSage, you will see that S1 refers to the gamma phase. The third line contains the graphite phase of carbon, and so forth. The purpose of this file is to tell *auxi* that materials based on this MDF will contain these compound phases, and nothing else.

Material description files can also contain material assays. The content of the “ilmenite.txt” MDF is shown here:

Compound	IlmeniteA	IlmeniteB	IlmeniteC
Al2O3[S1]	0.01160	0.01550	0.00941
CaO[S]	0.00022	0.00001	0.00017
Cr2O3[S]	0.00008	0.00022	0.00011
Fe2O3[S1]	0.20200	0.47300	0.49674
Fe3O4[S1]	0.00000	0.00000	0.00000
FeO[S]	0.27900	0.19100	0.00000
K2O[S]	0.00004	0.00001	0.00005
MgO[S]	0.01040	0.00580	0.01090
MnO[S]	0.00540	0.00480	0.00525
Na2O[S1]	0.00007	0.00005	0.00031
P4O10[S]	0.00001	0.00032	0.00015
SiO2[S1]	0.00850	0.00490	0.01744
TiO2[S1]	0.47700	0.29400	0.45949
V2O5[S]	0.00360	0.00800	0.00000

The first row still contains the word “Compound” as header for the list of compound phases. The subsequent words in the first row are assay names. **An assay name may not contain space or tab characters.** If it does, it will be interpreted as more than one name.

The first column of the file has the same meaning as the single column in the “mix.txt” file. It is a list of chemical compound phases that are allowed in materials based on this MDF. All subsequent columns contain assay information. Generally the numbers are mass fractions of the different component phases for the respective material assays. If you will be normalising your assays, the numbers can be masses, percentages or mass fractions, since they will be converted to mass fractions by normalisation.

There is more twist in the MDF tale. You can add your own custom material properties to the file. The “ilmenite.txt” file was modified to include prices for the different ilmenites:

Compound	IlmeniteA	IlmeniteB	IlmeniteC
Al2O3[S1]	0.01160	0.01550	0.00941
CaO[S]	0.00022	0.00001	0.00017
Cr2O3[S]	0.00008	0.00022	0.00011
Fe2O3[S1]	0.20200	0.47300	0.49674
Fe3O4[S1]	0.00000	0.00000	0.00000
FeO[S]	0.27900	0.19100	0.00000
K2O[S]	0.00004	0.00001	0.00005
MgO[S]	0.01040	0.00580	0.01090
MnO[S]	0.00540	0.00480	0.00525
Na2O[S1]	0.00007	0.00005	0.00031
P4O10[S]	0.00001	0.00032	0.00015
SiO2[S1]	0.00850	0.00490	0.01744
TiO2[S1]	0.47700	0.29400	0.45949
V2O5[S]	0.00360	0.00800	0.00000
#			
Price[USD/ton]	47.5000	32.2300	45.1400

The name of the property in this case is “Price” and its units are “USD/ton”. **There may be no spaces in the string containing the property name and units.** In this case the string is “Price[USD/ton]”, which serves the purpose of describing the custom property clearly.

**Be careful not to leave empty lines at the end of your material description file.** It tends to cause problems.

## Materials

Now that we have created a few material description files, we can create material objects in Python.

```

1 from auxi.modelling.process.materials.thermo import Material
2
3 ilmenite = Material("Ilmenite", "./materials/ilmenite.txt")
4 print(ilmenite)
5
6 reductant = Material("Reductant", "./materials/reductant.txt")
7 print(reductant)
8
9 mix = Material("Mix", "./materials/mix.txt")
10 print(mix)

```

The `Material` class is imported on line 1. On line 3 a `Material` object is created, specifying the name of the object as the first parameter, and the location and name of the material description file as the second parameter. Two more `Material` objects are created on lines 6 and 9. The materials are preted out after creation, with the following result:

=====			
Material			
=====			
Name	Ilmenite		
-----			
Composition Details (mass fractions)			
Compound	IlmeniteA	IlmeniteB	IlmeniteC
-----			
Al2O3[S1]	1.16000000e-02	1.55000000e-02	9.41000000e-03
CaO[S]	2.20000000e-04	1.00000000e-05	1.70000000e-04
Cr2O3[S]	8.00000000e-05	2.20000000e-04	1.10000000e-04
Fe2O3[S1]	2.02000000e-01	4.73000000e-01	4.96740000e-01
Fe3O4[S1]	0.00000000e+00	0.00000000e+00	0.00000000e+00
FeO[S]	2.79000000e-01	1.91000000e-01	0.00000000e+00
K2O[S]	4.00000000e-05	1.00000000e-05	5.00000000e-05
MgO[S]	1.04000000e-02	5.80000000e-03	1.09000000e-02
MnO[S]	5.40000000e-03	4.80000000e-03	5.25000000e-03
Na2O[S1]	7.00000000e-05	5.00000000e-05	3.10000000e-04
P4O10[S]	1.00000000e-05	3.20000000e-04	1.50000000e-04
SiO2[S1]	8.50000000e-03	4.90000000e-03	1.74400000e-02
TiO2[S1]	4.77000000e-01	2.94000000e-01	4.59490000e-01
V2O5[S]	3.60000000e-03	8.00000000e-03	0.00000000e+00
-----			
Custom Properties:			
-----			
Price[USD/ton]	4.75000000e+01	3.22300000e+01	4.51400000e+01
=====			
=====			
Material			
=====			
Name	Reductant		
-----			
Composition Details (mass fractions)			
Compound	ReductantA	ReductantB	
-----			
C[S1]	8.40973866e-01	1.00000000e+00	
H2[G]	1.37955186e-02	0.00000000e+00	
O2[G]	4.94339606e-02	0.00000000e+00	
N2[G]	6.09802120e-03	0.00000000e+00	
S[S1]	2.04933390e-03	0.00000000e+00	
Al2O3[S1]	1.20884160e-03	0.00000000e+00	
CaO[S]	2.94179980e-03	0.00000000e+00	
Fe2O3[S1]	7.85955656e-02	0.00000000e+00	
MgO[S]	1.41179360e-03	0.00000000e+00	
SiO2[S1]	3.49129950e-03	0.00000000e+00	

```

=====

=====
Material
=====
Name                      Mix
-----
Compound
-----
Al2O3[S1]
C[S1]
CaO[S]
Cr2O3[S]
Fe2O3[S1]
Fe3O4[S1]
FeO[S]
H2[G]
K2O[S]
MgO[S]
MnO[S]
Na2O[S1]
N2[G]
O2[G]
P4O10[S]
S[S1]
SiO2[S1]
TiO2[S1]
V2O5[S]
=====

```

The material objects are now ready to create material packages.

## Material Packages

### Creating Empty Packages

The simplest way to create material packages is to create empty ones.

```

1  from auxi.modelling.process.materials.thermo import Material
2
3  ilmenite = Material("Ilmenite", "./materials/ilmenite.txt")
4  reductant = Material("Reductant", "./materials/reductant.txt")
5  mix = Material("Mix", "./materials/mix.txt")
6
7  empty_ilmenite_package = ilmenite.create_package()
8  print(empty_ilmenite_package)
9
10 empty_reductant_package = reductant.create_package()
11 print(empty_reductant_package)

```

```

12
13 empty_mix_package = mix.create_package()
14 print(empty_mix_package)

```

The empty packages are created by calling the “create\_package” method of the Material objects without passing any parameters.

```

=====
MaterialPackage
=====
Material          Ilmenite
Mass              0.00000000e+00 kg
Amount           0.00000000e+00 kmol
Pressure         1.00000000e+00 atm
Temperature      2.50000000e+01 °C
Enthalpy         0.00000000e+00 kWh
-----
Compound Details
Formula          Mass          Mass Fraction    Mole Fraction
-----
Al2O3[S1]       0.00000000e+00    0.00000000e+00    0.00000000e+00
CaO[S]         0.00000000e+00    0.00000000e+00    0.00000000e+00
Cr2O3[S]       0.00000000e+00    0.00000000e+00    0.00000000e+00
Fe2O3[S1]     0.00000000e+00    0.00000000e+00    0.00000000e+00
Fe3O4[S1]     0.00000000e+00    0.00000000e+00    0.00000000e+00
FeO[S]        0.00000000e+00    0.00000000e+00    0.00000000e+00
K2O[S]        0.00000000e+00    0.00000000e+00    0.00000000e+00
MgO[S]        0.00000000e+00    0.00000000e+00    0.00000000e+00
MnO[S]        0.00000000e+00    0.00000000e+00    0.00000000e+00
Na2O[S1]     0.00000000e+00    0.00000000e+00    0.00000000e+00
P4O10[S]     0.00000000e+00    0.00000000e+00    0.00000000e+00
SiO2[S1]     0.00000000e+00    0.00000000e+00    0.00000000e+00
TiO2[S1]     0.00000000e+00    0.00000000e+00    0.00000000e+00
V2O5[S]      0.00000000e+00    0.00000000e+00    0.00000000e+00
=====

=====
MaterialPackage
=====
Material          Reductant
Mass              0.00000000e+00 kg
Amount           0.00000000e+00 kmol
Pressure         1.00000000e+00 atm
Temperature      2.50000000e+01 °C
Enthalpy         0.00000000e+00 kWh
-----
Compound Details
Formula          Mass          Mass Fraction    Mole Fraction
-----
C[S1]           0.00000000e+00    0.00000000e+00    0.00000000e+00

```

H2 [G]	0.00000000e+00	0.00000000e+00	0.00000000e+00
O2 [G]	0.00000000e+00	0.00000000e+00	0.00000000e+00
N2 [G]	0.00000000e+00	0.00000000e+00	0.00000000e+00
S [S1]	0.00000000e+00	0.00000000e+00	0.00000000e+00
Al2O3 [S1]	0.00000000e+00	0.00000000e+00	0.00000000e+00
CaO [S]	0.00000000e+00	0.00000000e+00	0.00000000e+00
Fe2O3 [S1]	0.00000000e+00	0.00000000e+00	0.00000000e+00
MgO [S]	0.00000000e+00	0.00000000e+00	0.00000000e+00
SiO2 [S1]	0.00000000e+00	0.00000000e+00	0.00000000e+00
=====			
MaterialPackage			
=====			
Material	Mix		
Mass	0.00000000e+00	kg	
Amount	0.00000000e+00	kmol	
Pressure	1.00000000e+00	atm	
Temperature	2.50000000e+01	°C	
Enthalpy	0.00000000e+00	kWh	
-----			
Compound Details			
Formula	Mass	Mass Fraction	Mole Fraction
-----			
Al2O3 [S1]	0.00000000e+00	0.00000000e+00	0.00000000e+00
C [S1]	0.00000000e+00	0.00000000e+00	0.00000000e+00
CaO [S]	0.00000000e+00	0.00000000e+00	0.00000000e+00
Cr2O3 [S]	0.00000000e+00	0.00000000e+00	0.00000000e+00
Fe2O3 [S1]	0.00000000e+00	0.00000000e+00	0.00000000e+00
Fe3O4 [S1]	0.00000000e+00	0.00000000e+00	0.00000000e+00
FeO [S]	0.00000000e+00	0.00000000e+00	0.00000000e+00
H2 [G]	0.00000000e+00	0.00000000e+00	0.00000000e+00
K2O [S]	0.00000000e+00	0.00000000e+00	0.00000000e+00
MgO [S]	0.00000000e+00	0.00000000e+00	0.00000000e+00
MnO [S]	0.00000000e+00	0.00000000e+00	0.00000000e+00
Na2O [S1]	0.00000000e+00	0.00000000e+00	0.00000000e+00
N2 [G]	0.00000000e+00	0.00000000e+00	0.00000000e+00
O2 [G]	0.00000000e+00	0.00000000e+00	0.00000000e+00
P4O10 [S]	0.00000000e+00	0.00000000e+00	0.00000000e+00
S [S1]	0.00000000e+00	0.00000000e+00	0.00000000e+00
SiO2 [S1]	0.00000000e+00	0.00000000e+00	0.00000000e+00
TiO2 [S1]	0.00000000e+00	0.00000000e+00	0.00000000e+00
V2O5 [S]	0.00000000e+00	0.00000000e+00	0.00000000e+00
=====			

## Creating Filled Packages

It is just as easy to create packages that contain some mass. Let's do that with ilmenite.

```

1 from auxi.modelling.process.materials.thermo import Material
2
3 ilmenite = Material("Ilmenite", "./materials/ilmenite.txt")
4 reductant = Material("Reductant", "./materials/reductant.txt")
5 mix = Material("Mix", "./materials/mix.txt")
6
7 ilma_package = ilmenite.create_package("IlmeniteA", 300.0, 1.0, 25.
  ↪0)
8 print(ilma_package)

```

The parameters to the “create\_package” method are:

1. material assay name, “IlmeniteA”
2. mass, 300 kg
3. pressure, 1 atm
4. temperature, 25 °C

We therefore created 300 kg based on the composition specified by the IlmeniteA assay, at 1 atm pressure and 25 °C temperature. The resulting package is shown here.

```

=====
MaterialPackage
=====
Material          Ilmenite
Mass              3.00000000e+02 kg
Amount           3.52817004e+00 kmol
Pressure          1.00000000e+00 atm
Temperature       2.50000000e+01 °C
Enthalpy         -6.87812118e+02 kWh
-----
Compound Details
Formula           Mass           Mass Fraction   Mole Fraction
-----
Al2O3[S1]         3.48725349e+00   1.16241783e-02   9.69390473e-03
CaO[S]            6.61375661e-02   2.20458554e-04   3.34280337e-04
Cr2O3[S]          2.40500241e-02   8.01667468e-05   4.48486990e-05
Fe2O3[S1]         6.07263107e+01   2.02421036e-01   1.07784066e-01
Fe3O4[S1]         0.00000000e+00   0.00000000e+00   0.00000000e+00
FeO[S]            8.38744589e+01   2.79581530e-01   3.30892788e-01
K2O[S]            1.20250120e-02   4.00833734e-05   3.61829148e-05
MgO[S]            3.12650313e+00   1.04216771e-02   2.19865404e-02
MnO[S]            1.62337662e+00   5.41125541e-03   6.48625791e-03
Na2O[S1]          2.10437710e-02   7.01459035e-05   9.62343053e-05
P4O10[S]          3.00625301e-03   1.00208434e-05   3.00142421e-06
SiO2[S1]          2.55531506e+00   8.51771685e-03   1.20540764e-02
TiO2[S1]          1.43398268e+02   4.77994228e-01   5.08901291e-01
V2O5[S]           1.08225108e+00   3.60750361e-03   1.68652807e-03
=====

```



## Adding Material to a Package - Another Package

Now we create another ilmenite package with a different composition, mass and temperature, and add it to the first:

```

1 from auxi.modelling.process.materials.thermo import Material
2
3 ilmenite = Material("Ilmenite", "./materials/ilmenite.txt")
4 reductant = Material("Reductant", "./materials/reductant.txt")
5 mix = Material("Mix", "./materials/mix.txt")
6
7 ilma_package = ilmenite.create_package("IlmeniteA", 300.0, 1.0, 25.
8     ↪0)
9
10 ilmb_package = ilmenite.create_package("IlmeniteB", 500.0, 1.0, 750.
11     ↪0)
12
13 ilma_package += ilmb_package
14 print(ilma_package)
15 print(ilmb_package)

```

This changes the original “ilma\_package”, but the second “ilmb\_package” remains the same. This is quite a powerful action, since one line of code does all of the following:

- Calculate the total mass of each component by adding up the component masses from the two packages.
- Calculate the mass fraction of each compound.
- Calculate the mole fraction of each compound.
- Calculate the total amount (in kmol) of compounds in the package.
- Calculate the total enthalpy by adding up the enthalpies of the two original packages.
- Calculate the temperature of the new package.

The resulting two packages are shown below:

```

=====
MaterialPackage
=====
Material          Ilmenite
Mass              8.00000000e+02 kg
Amount           8.43715862e+00 kmol
Pressure          1.00000000e+00 atm
Temperature       4.88474167e+02 °C
Enthalpy          -1.59326344e+03 kWh
-----
Compound Details
Formula           Mass              Mass Fraction    Mole Fraction
-----
Al2O3[S1]         1.12558204e+01   1.40697755e-02   1.30841549e-02
CaO[S]            7.11495448e-02   8.89369310e-05   1.50379294e-04

```

Cr2O3[S]	1.34313554e-01	1.67891942e-04	1.04738770e-04
Fe2O3[S1]	2.97792900e+02	3.72241125e-01	2.21026985e-01
Fe3O4[S1]	0.00000000e+00	0.00000000e+00	0.00000000e+00
FeO[S]	1.79603251e+02	2.24504063e-01	2.96295501e-01
K2O[S]	1.70369907e-02	2.12962383e-05	2.14370100e-05
MgO[S]	6.03345073e+00	7.54181341e-03	1.77425932e-02
MnO[S]	4.02912637e+00	5.03640796e-03	6.73192250e-03
Na2O[S1]	4.61036642e-02	5.76295802e-05	8.81647712e-05
P4O10[S]	1.63389569e-01	2.04236961e-04	6.82149359e-05
SiO2[S1]	5.01118458e+00	6.26398073e-03	9.88514810e-03
TiO2[S1]	2.90750440e+02	3.63438050e-01	4.31482633e-01
V2O5[S]	5.09183399e+00	6.36479248e-03	3.31812755e-03
=====			
MaterialPackage			
=====			
Material	Ilmenite		
Mass	5.00000000e+02	kg	
Amount	4.90898858e+00	kmol	
Pressure	1.00000000e+00	atm	
Temperature	7.50000000e+02	°C	
Enthalpy	-9.05451326e+02	kWh	
-----			
Compound Details			
Formula	Mass	Mass Fraction	Mole Fraction
-----			
Al2O3[S1]	7.76856687e+00	1.55371337e-02	1.55207829e-02
CaO[S]	5.01197863e-03	1.00239573e-05	1.82066196e-05
Cr2O3[S]	1.10263530e-01	2.20527060e-04	1.47782739e-04
Fe2O3[S1]	2.37066589e+02	4.74133178e-01	3.02416515e-01
Fe3O4[S1]	0.00000000e+00	0.00000000e+00	0.00000000e+00
FeO[S]	9.57287918e+01	1.91457584e-01	2.71429867e-01
K2O[S]	5.01197863e-03	1.00239573e-05	1.08388880e-05
MgO[S]	2.90694760e+00	5.81389521e-03	1.46923993e-02
MnO[S]	2.40574974e+00	4.81149948e-03	6.90848565e-03
Na2O[S1]	2.50598931e-02	5.01197863e-05	8.23650657e-05
P4O10[S]	1.60383316e-01	3.20766632e-04	1.15084949e-04
SiO2[S1]	2.45586953e+00	4.91173906e-03	8.32630400e-03
TiO2[S1]	1.47352172e+02	2.94704343e-01	3.75840583e-01
V2O5[S]	4.00958290e+00	8.01916581e-03	4.49078466e-03
=====			

## Adding Material to a Package - A Compound Mass

Sometimes you need to add material to a package, one compound at a time.

```
1 from auxi.modelling.process.materials.thermo import Material
2
```

```

3  ilmenite = Material("Ilmenite", "./materials/ilmenite.txt")
4  reductant = Material("Reductant", "./materials/reductant.txt")
5  mix = Material("Mix", "./materials/mix.txt")
6
7  ilma_package = ilmenite.create_package("IlmeniteA", 300.0, 1.0, 25.
   ↪0)
8
9  ilma_package += ("TiO2[S1]", 150.0)
10 print(ilma_package)

```

This adds 150 kg of TiO2[S1] to ilma\_package. The temperature of the added material is assumed to be the same as that of the original package, which means that ilma\_package's temperature does not change. Here is the result:

```

=====
MaterialPackage
=====
Material          Ilmenite
Mass              4.50000000e+02 kg
Amount           5.40632064e+00 kmol
Pressure         1.00000000e+00 atm
Temperature      2.50000000e+01 °C
Enthalpy         -1.18069622e+03 kWh
-----
Compound Details
Formula          Mass          Mass Fraction    Mole Fraction
-----
Al2O3[S1]       3.48725349e+00    7.74945219e-03    6.32625154e-03
CaO[S]          6.61375661e-02    1.46972369e-04    2.18151669e-04
Cr2O3[S]        2.40500241e-02    5.34444979e-05    2.92683040e-05
Fe2O3[S1]       6.07263107e+01    1.34947357e-01    7.03399852e-02
Fe3O4[S1]       0.00000000e+00    0.00000000e+00    0.00000000e+00
FeO[S]          8.38744589e+01    1.86387686e-01    2.15940951e-01
K2O[S]          1.20250120e-02    2.67222489e-05    2.36130050e-05
MgO[S]          3.12650313e+00    6.94778473e-03    1.43484374e-02
MnO[S]          1.62337662e+00    3.60750361e-03    4.23293814e-03
Na2O[S1]        2.10437710e-02    4.67639357e-05    6.28026001e-05
P4O10[S]        3.00625301e-03    6.68056224e-06    1.95873232e-06
SiO2[S1]        2.55531506e+00    5.67847790e-03    7.86650184e-03
TiO2[S1]        2.93398268e+02    6.51996152e-01    6.79508511e-01
V2O5[S]         1.08225108e+00    2.40500241e-03    1.10062984e-03
=====

```

### Adding Material to a Package - A Compound Mass with Specified Temperature

We can also add a certain mass of a specified compound at a temperature different from the original package.

```

1 from auxi.modelling.process.materials.thermo import Material
2
3 ilmenite = Material("Ilmenite", "./materials/ilmenite.txt")
4 reductant = Material("Reductant", "./materials/reductant.txt")
5 mix = Material("Mix", "./materials/mix.txt")
6
7 ilma_package = ilmenite.create_package("IlmeniteA", 300.0, 1.0, 25.
8     ↪0)
9
10 ilma_package += ("TiO2[S1]", 150.0, 1000.0)
11 print(ilma_package)

```

This action calculates a new total mass, component masses, mass fractions and mole fractions, as well as a new enthalpy and temperature.

```

=====
MaterialPackage
=====
Material           Ilmenite
Mass               4.50000000e+02 kg
Amount            5.40632064e+00 kmol
Pressure           1.00000000e+00 atm
Temperature        3.84927151e+02 °C
Enthalpy           -1.14449836e+03 kWh
-----
Compound Details
Formula            Mass                Mass Fraction    Mole Fraction
-----
Al2O3[S1]          3.48725349e+00    7.74945219e-03    6.32625154e-03
CaO[S]             6.61375661e-02    1.46972369e-04    2.18151669e-04
Cr2O3[S]           2.40500241e-02    5.34444979e-05    2.92683040e-05
Fe2O3[S1]          6.07263107e+01    1.34947357e-01    7.03399852e-02
Fe3O4[S1]          0.00000000e+00    0.00000000e+00    0.00000000e+00
FeO[S]             8.38744589e+01    1.86387686e-01    2.15940951e-01
K2O[S]             1.20250120e-02    2.67222489e-05    2.36130050e-05
MgO[S]             3.12650313e+00    6.94778473e-03    1.43484374e-02
MnO[S]             1.62337662e+00    3.60750361e-03    4.23293814e-03
Na2O[S1]           2.10437710e-02    4.67639357e-05    6.28026001e-05
P4O10[S]           3.00625301e-03    6.68056224e-06    1.95873232e-06
SiO2[S1]           2.55531506e+00    5.67847790e-03    7.86650184e-03
TiO2[S1]           2.93398268e+02    6.51996152e-01    6.79508511e-01
V2O5[S]            1.08225108e+00    2.40500241e-03    1.10062984e-03
=====

```

## Adding Packages of Different Materials Together

We very often need to add packages from different materials together. For example, ilmenite and reductant can be added together so that reduction reactions can be modelled.

```

1 from auxi.modelling.process.materials.thermo import Material
2
3 ilmenite = Material("Ilmenite", "./materials/ilmenite.txt")
4 reductant = Material("Reductant", "./materials/reductant.txt")
5 mix = Material("Mix", "./materials/mix.txt")
6
7 ilma_package = ilmenite.create_package("IlmeniteA", 300.0, 1.0, 25.
8     ↪0)
9 reda_package = reductant.create_package("ReductantA", 35.0, 1.0, 25.
10    ↪0)
11 new_package = ilma_package + reda_package
12 print(new_package)

```

This, however, does not work. See the last two lines of the error message below.

```

Traceback (most recent call last):
File "test.py", line 10, in <module>
    new_package = ilma_package + reda_package
File "thermochemistry.material.py", line 430, in __add__
    self.material.name + "'.")
Exception: Packages of 'Reductant' cannot be added to packages of
↪ 'Ilmenite'.
    The compound 'C[S1]' was not found in 'Ilmenite'.

```

Let's try it by swapping the two material packages around.

```

1 from auxi.modelling.process.materials.thermo import Material
2
3 ilmenite = Material("Ilmenite", "./materials/ilmenite.txt")
4 reductant = Material("Reductant", "./materials/reductant.txt")
5 mix = Material("Mix", "./materials/mix.txt")
6
7 ilma_package = ilmenite.create_package("IlmeniteA", 300.0, 1.0, 25.
8     ↪0)
9 reda_package = reductant.create_package("ReductantA", 35.0, 1.0, 25.
10    ↪0)
11 new_package = reda_package + ilma_package
12 print(new_package)

```

```

Traceback (most recent call last):
File "test.py", line 10, in <module>
    new_package = reda_package + ilma_package
File "thermochemistry.material.py", line 430, in __add__
    self.material.name + "'.")
Exception: Packages of 'Ilmenite' cannot be added to packages of
↪ 'Reductant'.
    The compound 'Cr2O3[S]' was not found in 'Reductant'.

```

Still no luck. These packages cannot be added together because their materials are not compatible. We need to use an intermediate material package from a compatible material that will allow us to add ilmenite and reductant together. This is the purpose of the “mix” material that we created early on.

```

1 from auxi.modelling.process.materials.thermo import Material
2
3 ilmenite = Material("Ilmenite", "./materials/ilmenite.txt")
4 reductant = Material("Reductant", "./materials/reductant.txt")
5 mix = Material("Mix", "./materials/mix.txt")
6
7 ilma_package = ilmenite.create_package("IlmeniteA", 300.0, 1.0, 25.
8     ↪0)
9 reda_package = reductant.create_package("ReductantA", 35.0, 1.0, 25.
10    ↪0)
11
12 new_package = mix.create_package()
13 new_package += ilma_package
14 new_package += reda_package
15 print(new_package)

```

Success at last! The mix material package is able to receive all the compound masses from both the ilmenite and reductant packages.

```

=====
MaterialPackage
=====
Material          Mix
Mass              3.35000000e+02 kg
Amount           6.30500835e+00 kmol
Pressure          1.00000000e+00 atm
Temperature       2.50000000e+01 °C
Enthalpy          -6.92925041e+02 kWh
-----
Compound Details
Formula           Mass           Mass Fraction   Mole Fraction
-----
Al2O3[S1]         3.52956294e+00   1.05360088e-02   5.49034965e-03
C[S1]             2.94340853e+01   8.78629412e-02   3.88683906e-01
CaO[S]            1.69100559e-01   5.04777788e-04   4.78268203e-04
Cr2O3[S]          2.40500241e-02   7.17911166e-05   2.50965308e-05
Fe2O3[S1]         6.34771555e+01   1.89484046e-01   6.30462073e-02
Fe3O4[S1]         0.00000000e+00   0.00000000e+00   0.00000000e+00
FeO[S]            8.38744589e+01   2.50371519e-01   1.85161693e-01
H2[G]             4.82843151e-01   1.44132284e-03   3.79888138e-02
K2O[S]            1.20250120e-02   3.58955583e-05   2.02473128e-05
MgO[S]            3.17591590e+00   9.48034598e-03   1.24977222e-02
MnO[S]            1.62337662e+00   4.84590037e-03   3.62959406e-03
Na2O[S1]          2.10437710e-02   6.28172270e-05   5.38509982e-05
N2[G]             2.13430742e-01   6.37106693e-04   1.20838199e-03
O2[G]             1.73018862e+00   5.16474215e-03   8.57578913e-03

```

P4O10[S]	3.00625301e-03	8.97388957e-06	1.67954337e-06
S[S1]	7.17266865e-02	2.14109512e-04	3.54772799e-04
SiO2[S1]	2.67751054e+00	7.99256877e-03	7.06780432e-03
TiO2[S1]	1.43398268e+02	4.28054533e-01	2.84772072e-01
V2O5[S]	1.08225108e+00	3.23060025e-03	9.43750984e-04
=====			

## Adding Material Together - Package + Package

In the above three sections we demonstrated how material can be added to an existing package. Here we will add material together to create a new package.

```

1 from auxi.modelling.process.materials.thermo import Material
2
3 ilmenite = Material("Ilmenite", "./materials/ilmenite.txt")
4 reductant = Material("Reductant", "./materials/reductant.txt")
5 mix = Material("Mix", "./materials/mix.txt")
6
7 ilma_package = ilmenite.create_package("IlmeniteA", 300.0, 1.0, 25.
8     ↪0)
9 ilmb_package = ilmenite.create_package("IlmeniteB", 500.0, 1.0, 750.
10    ↪0)
11
12 new_package = ilma_package + ilmb_package
13 print(new_package)

```

This action performs all the calculations to create a new package with properties based on the two original packages. Specifically note that the temperature was automatically calculated.

```

=====
MaterialPackage
=====
Material          Ilmenite
Mass              8.00000000e+02 kg
Amount           8.43715862e+00 kmol
Pressure         1.00000000e+00 atm
Temperature      4.88474167e+02 °C
Enthalpy        -1.59326344e+03 kWh
-----
Compound Details
Formula          Mass          Mass Fraction    Mole Fraction
-----
Al2O3[S1]       1.12558204e+01    1.40697755e-02    1.30841549e-02
CaO[S]          7.11495448e-02    8.89369310e-05    1.50379294e-04
Cr2O3[S]        1.34313554e-01    1.67891942e-04    1.04738770e-04
Fe2O3[S1]       2.97792900e+02    3.72241125e-01    2.21026985e-01
Fe3O4[S1]       0.00000000e+00    0.00000000e+00    0.00000000e+00
FeO[S]          1.79603251e+02    2.24504063e-01    2.96295501e-01
K2O[S]          1.70369907e-02    2.12962383e-05    2.14370100e-05

```

MgO[S]	6.03345073e+00	7.54181341e-03	1.77425932e-02
MnO[S]	4.02912637e+00	5.03640796e-03	6.73192250e-03
Na2O[S1]	4.61036642e-02	5.76295802e-05	8.81647712e-05
P4O10[S]	1.63389569e-01	2.04236961e-04	6.82149359e-05
SiO2[S1]	5.01118458e+00	6.26398073e-03	9.88514810e-03
TiO2[S1]	2.90750440e+02	3.63438050e-01	4.31482633e-01
V2O5[S]	5.09183399e+00	6.36479248e-03	3.31812755e-03
=====			

## Adding Material Together - Package + Compound Mass

Now we add a package and specific mass of a compound together to produce a new package.

```

1 from auxi.modelling.process.materials.thermo import Material
2
3 ilmenite = Material("Ilmenite", "./materials/ilmenite.txt")
4 reductant = Material("Reductant", "./materials/reductant.txt")
5 mix = Material("Mix", "./materials/mix.txt")
6
7 ilma_package = ilmenite.create_package("IlmeniteA", 300.0, 1.0, 25.
8     ↪0)
9
10 new_package = ilma_package + ("TiO2[S1]", 150.0)
11 print(new_package)

```

The added compound mass is assumed to be at the same temperature as the original package. This results in the new package having the same temperature as the original package.

```

=====
MaterialPackage
=====
Material          Ilmenite
Mass              4.50000000e+02 kg
Amount           5.40632064e+00 kmol
Pressure         1.00000000e+00 atm
Temperature      2.50000000e+01 °C
Enthalpy        -1.18069622e+03 kWh
-----
Compound Details
Formula          Mass          Mass Fraction    Mole Fraction
-----
Al2O3[S1]       3.48725349e+00    7.74945219e-03    6.32625154e-03
CaO[S]          6.61375661e-02    1.46972369e-04    2.18151669e-04
Cr2O3[S]        2.40500241e-02    5.34444979e-05    2.92683040e-05
Fe2O3[S1]       6.07263107e+01    1.34947357e-01    7.03399852e-02
Fe3O4[S1]       0.00000000e+00    0.00000000e+00    0.00000000e+00
FeO[S]          8.38744589e+01    1.86387686e-01    2.15940951e-01
K2O[S]          1.20250120e-02    2.67222489e-05    2.36130050e-05
MgO[S]          3.12650313e+00    6.94778473e-03    1.43484374e-02

```



MnO[S]	1.62337662e+00	3.60750361e-03	4.23293814e-03
Na2O[S1]	2.10437710e-02	4.67639357e-05	6.28026001e-05
P4O10[S]	3.00625301e-03	6.68056224e-06	1.95873232e-06
SiO2[S1]	2.55531506e+00	5.67847790e-03	7.86650184e-03
TiO2[S1]	2.93398268e+02	6.51996152e-01	6.79508511e-01
V2O5[S]	1.08225108e+00	2.40500241e-03	1.10062984e-03
=====			

## Adding Material Together - Package + Compound Mass at Specified Temperature

Now we add the same compound mass as in the previous section, but at a different temperature.

```

1 from auxi.materials.thermo import Material
2
3 ilmenite = Material("Ilmenite", "./materials/ilmenite.txt")
4 reductant = Material("Reductant", "./materials/reductant.txt")
5 mix = Material("Mix", "./materials/mix.txt")
6
7 ilma_package = ilmenite.create_package("IlmeniteA", 300.0, 1.0, 25.
8     ↪0)
9
10 new_package = ilma_package + ("TiO2[S1]", 150.0, 1000.0)
11 print(new_package)

```

The new package now has a different temperature, which is calculated based on the enthalpy of the original package and the enthalpy of the added compound mass.

=====			
MaterialPackage			
=====			
Material	Ilmenite		
Mass	4.50000000e+02	kg	
Amount	5.40632064e+00	kmol	
Pressure	1.00000000e+00	atm	
Temperature	3.84927151e+02	°C	
Enthalpy	-1.14449836e+03	kWh	
-----			
Compound Details			
Formula	Mass	Mass Fraction	Mole Fraction
-----			
Al2O3[S1]	3.48725349e+00	7.74945219e-03	6.32625154e-03
CaO[S]	6.61375661e-02	1.46972369e-04	2.18151669e-04
Cr2O3[S]	2.40500241e-02	5.34444979e-05	2.92683040e-05
Fe2O3[S1]	6.07263107e+01	1.34947357e-01	7.03399852e-02
Fe3O4[S1]	0.00000000e+00	0.00000000e+00	0.00000000e+00
FeO[S]	8.38744589e+01	1.86387686e-01	2.15940951e-01
K2O[S]	1.20250120e-02	2.67222489e-05	2.36130050e-05
MgO[S]	3.12650313e+00	6.94778473e-03	1.43484374e-02
MnO[S]	1.62337662e+00	3.60750361e-03	4.23293814e-03

Na2O[S1]	2.10437710e-02	4.67639357e-05	6.28026001e-05
P4O10[S]	3.00625301e-03	6.68056224e-06	1.95873232e-06
SiO2[S1]	2.55531506e+00	5.67847790e-03	7.86650184e-03
TiO2[S1]	2.93398268e+02	6.51996152e-01	6.79508511e-01
V2O5[S]	1.08225108e+00	2.40500241e-03	1.10062984e-03
=====			

## Extract Material from a Package - Mass

When we need to create a new package by extracting material from an existing material, we use the “extract” method. First of all we can simply specify the total mass to be extracted.

```

1 from auxi.modelling.process.materials.thermo import Material
2
3 ilmenite = Material("Ilmenite", "./materials/ilmenite.txt")
4 reductant = Material("Reductant", "./materials/reductant.txt")
5 mix = Material("Mix", "./materials/mix.txt")
6
7 ilma_package = ilmenite.create_package("IlmeniteA", 300.0, 1.0, 25.
8     ↪0)
9
10 new_package = ilma_package.extract(75.0)
11 print(ilma_package)
12 print(new_package)

```

This removes 75 kg from the original package, and produces a new package of 75 kg. The new package has the same composition, temperature and pressure as the original one.

```

=====
MaterialPackage
=====
Material          Ilmenite
Mass              2.25000000e+02 kg
Amount           2.64612753e+00 kmol
Pressure         1.00000000e+00 atm
Temperature      2.50000000e+01 °C
Enthalpy        -5.15859089e+02 kWh
-----
Compound Details
Formula          Mass          Mass Fraction    Mole Fraction
-----
Al2O3[S1]       2.61544012e+00    1.16241783e-02    9.69390473e-03
CaO[S]          4.96031746e-02    2.20458554e-04    3.34280337e-04
Cr2O3[S]        1.80375180e-02    8.01667468e-05    4.48486990e-05
Fe2O3[S1]       4.55447330e+01    2.02421036e-01    1.07784066e-01
Fe3O4[S1]       0.00000000e+00    0.00000000e+00    0.00000000e+00
FeO[S]          6.29058442e+01    2.79581530e-01    3.30892788e-01
K2O[S]          9.01875902e-03    4.00833734e-05    3.61829148e-05
MgO[S]          2.34487734e+00    1.04216771e-02    2.19865404e-02

```

```

MnO[S]          1.21753247e+00  5.41125541e-03  6.48625791e-03
Na2O[S1]        1.57828283e-02  7.01459035e-05  9.62343053e-05
P4O10[S]        2.25468975e-03  1.00208434e-05  3.00142421e-06
SiO2[S1]        1.91648629e+00  8.51771685e-03  1.20540764e-02
TiO2[S1]        1.07548701e+02  4.77994228e-01  5.08901291e-01
V2O5[S]         8.11688312e-01  3.60750361e-03  1.68652807e-03
=====

=====
MaterialPackage
=====
Material          Ilmenite
Mass              7.50000000e+01 kg
Amount           8.82042511e-01 kmol
Pressure         1.00000000e+00 atm
Temperature      2.50000000e+01 °C
Enthalpy         -1.71953030e+02 kWh
-----
Compound Details
Formula          Mass          Mass Fraction    Mole Fraction
-----
Al2O3[S1]       8.71813372e-01  1.16241783e-02  9.69390473e-03
CaO[S]          1.65343915e-02  2.20458554e-04  3.34280337e-04
Cr2O3[S]        6.01250601e-03  8.01667468e-05  4.48486990e-05
Fe2O3[S1]       1.51815777e+01  2.02421036e-01  1.07784066e-01
Fe3O4[S1]       0.00000000e+00  0.00000000e+00  0.00000000e+00
FeO[S]          2.09686147e+01  2.79581530e-01  3.30892788e-01
K2O[S]          3.00625301e-03  4.00833734e-05  3.61829148e-05
MgO[S]          7.81625782e-01  1.04216771e-02  2.19865404e-02
MnO[S]          4.05844156e-01  5.41125541e-03  6.48625791e-03
Na2O[S1]        5.26094276e-03  7.01459035e-05  9.62343053e-05
P4O10[S]        7.51563252e-04  1.00208434e-05  3.00142421e-06
SiO2[S1]        6.38828764e-01  8.51771685e-03  1.20540764e-02
TiO2[S1]        3.58495671e+01  4.77994228e-01  5.08901291e-01
V2O5[S]         2.70562771e-01  3.60750361e-03  1.68652807e-03
=====

```

## Extract Material from a Package - Compound

We can also extract all the mass of a single compound from an existing package into a new one.

```

1 from auxi.modelling.process.materials.thermo import Material
2
3 ilmenite = Material("Ilmenite", "./materials/ilmenite.txt")
4 reductant = Material("Reductant", "./materials/reductant.txt")
5 mix = Material("Mix", "./materials/mix.txt")
6
7 ilma_package = ilmenite.create_package("IlmeniteA", 300.0, 1.0, 25.
  ↪0)

```

```

8
9 new_package = ilma_package.extract("TiO2[S1]")
10 print(ilma_package)
11 print(new_package)

```

This modifies the original package's composition and enthalpy, and creates a new package of the same temperature consisting purely of the specified compound.

```

=====
MaterialPackage
=====
Material          Ilmenite
Mass              1.56601732e+02 kg
Amount           1.73267975e+00 kmol
Pressure          1.00000000e+00 atm
Temperature       2.50000000e+01 °C
Enthalpy         -2.16620609e+02 kWh
-----
Compound Details
Formula           Mass              Mass Fraction    Mole Fraction
-----
Al2O3[S1]         3.48725349e+00    2.22682946e-02    1.97392185e-02
CaO[S]            6.61375661e-02    4.22329724e-04    6.80678509e-04
Cr2O3[S]          2.40500241e-02    1.53574445e-04    9.13231864e-05
Fe2O3[S1]         6.07263107e+01    3.87775474e-01    2.19475361e-01
Fe3O4[S1]         0.00000000e+00    0.00000000e+00    0.00000000e+00
FeO[S]            8.38744589e+01    5.35590878e-01    6.73780610e-01
K2O[S]            1.20250120e-02    7.67872226e-05    7.36774791e-05
MgO[S]            3.12650313e+00    1.99646779e-02    4.47701043e-02
MnO[S]            1.62337662e+00    1.03662751e-02    1.32076460e-02
Na2O[S1]          2.10437710e-02    1.34377640e-04    1.95957154e-04
P4O10[S]          3.00625301e-03    1.91968057e-05    6.11165160e-06
SiO2[S1]          2.55531506e+00    1.63172848e-02    2.45451193e-02
TiO2[S1]          0.00000000e+00    0.00000000e+00    0.00000000e+00
V2O5[S]           1.08225108e+00    6.91085003e-03    3.43419366e-03
=====

=====
MaterialPackage
=====
Material          Ilmenite
Mass              1.43398268e+02 kg
Amount           1.79549029e+00 kmol
Pressure          1.00000000e+00 atm
Temperature       2.50000000e+01 °C
Enthalpy         -4.71191509e+02 kWh
-----
Compound Details
Formula           Mass              Mass Fraction    Mole Fraction
-----

```

Al2O3[S1]	0.00000000e+00	0.00000000e+00	0.00000000e+00
CaO[S]	0.00000000e+00	0.00000000e+00	0.00000000e+00
Cr2O3[S]	0.00000000e+00	0.00000000e+00	0.00000000e+00
Fe2O3[S1]	0.00000000e+00	0.00000000e+00	0.00000000e+00
Fe3O4[S1]	0.00000000e+00	0.00000000e+00	0.00000000e+00
FeO[S]	0.00000000e+00	0.00000000e+00	0.00000000e+00
K2O[S]	0.00000000e+00	0.00000000e+00	0.00000000e+00
MgO[S]	0.00000000e+00	0.00000000e+00	0.00000000e+00
MnO[S]	0.00000000e+00	0.00000000e+00	0.00000000e+00
Na2O[S1]	0.00000000e+00	0.00000000e+00	0.00000000e+00
P4O10[S]	0.00000000e+00	0.00000000e+00	0.00000000e+00
SiO2[S1]	0.00000000e+00	0.00000000e+00	0.00000000e+00
TiO2[S1]	1.43398268e+02	1.00000000e+00	1.00000000e+00
V2O5[S]	0.00000000e+00	0.00000000e+00	0.00000000e+00
=====			

## Extract Material from a Package - Compound Mass

We may not want to extract all the mass of a specific compound. In this case we can specify the mass to extract.

```

1 from auxi.modelling.process.materials.thermo import Material
2
3 ilmenite = Material("Ilmenite", "./materials/ilmenite.txt")
4 reductant = Material("Reductant", "./materials/reductant.txt")
5 mix = Material("Mix", "./materials/mix.txt")
6
7 ilma_package = ilmenite.create_package("IlmeniteA", 300.0, 1.0, 25.
8     ↪0)
9
10 new_package = ilma_package.extract(("TiO2[S1]", 110.0))
11 print(ilma_package)
12 print(new_package)

```

The existing package is modified appropriately and a new package containing only the specified mass of the required compound is produced.

=====			
MaterialPackage			
=====			
Material	Ilmenite		
Mass	1.90000000e+02	kg	
Amount	2.15085961e+00	kmol	
Pressure	1.00000000e+00	atm	
Temperature	2.50000000e+01	°C	
Enthalpy	-3.26363778e+02	kWh	
-----			
Compound Details			
Formula	Mass	Mass Fraction	Mole Fraction

```

-----
Al2O3[S1]      3.48725349e+00  1.83539657e-02  1.59014304e-02
CaO[S]        6.61375661e-02  3.48092453e-04  5.48337915e-04
Cr2O3[S]      2.40500241e-02  1.26579074e-04  7.35677195e-05
Fe2O3[S1]     6.07263107e+01  3.19612162e-01  1.76803968e-01
Fe3O4[S1]     0.00000000e+00  0.00000000e+00  0.00000000e+00
FeO[S]        8.38744589e+01  4.41444520e-01  5.42781136e-01
K2O[S]        1.20250120e-02  6.32895370e-05  5.93527704e-05
MgO[S]        3.12650313e+00  1.64552796e-02  3.60656982e-02
MnO[S]        1.62337662e+00  8.54408749e-03  1.06397557e-02
Na2O[S1]      2.10437710e-02  1.10756690e-04  1.57858278e-04
P4O10[S]      3.00625301e-03  1.58223842e-05  4.92339666e-06
SiO2[S1]      2.55531506e+00  1.34490266e-02  1.97729462e-02
TiO2[S1]      3.33982684e+01  1.75780360e-01  1.94424522e-01
V2O5[S]       1.08225108e+00  5.69605833e-03  2.76650220e-03
=====

```

#### MaterialPackage

```

=====
Material      Ilmenite
Mass          1.10000000e+02 kg
Amount        1.37731044e+00 kmol
Pressure      1.00000000e+00 atm
Temperature   2.50000000e+01 °C
Enthalpy      -3.61448340e+02 kWh
=====

```

#### Compound Details

Formula	Mass	Mass Fraction	Mole Fraction
Al2O3[S1]	0.00000000e+00	0.00000000e+00	0.00000000e+00
CaO[S]	0.00000000e+00	0.00000000e+00	0.00000000e+00
Cr2O3[S]	0.00000000e+00	0.00000000e+00	0.00000000e+00
Fe2O3[S1]	0.00000000e+00	0.00000000e+00	0.00000000e+00
Fe3O4[S1]	0.00000000e+00	0.00000000e+00	0.00000000e+00
FeO[S]	0.00000000e+00	0.00000000e+00	0.00000000e+00
K2O[S]	0.00000000e+00	0.00000000e+00	0.00000000e+00
MgO[S]	0.00000000e+00	0.00000000e+00	0.00000000e+00
MnO[S]	0.00000000e+00	0.00000000e+00	0.00000000e+00
Na2O[S1]	0.00000000e+00	0.00000000e+00	0.00000000e+00
P4O10[S]	0.00000000e+00	0.00000000e+00	0.00000000e+00
SiO2[S1]	0.00000000e+00	0.00000000e+00	0.00000000e+00
TiO2[S1]	1.10000000e+02	1.00000000e+00	1.00000000e+00
V2O5[S]	0.00000000e+00	0.00000000e+00	0.00000000e+00

## Extract Material from a Package - Material

We may need to extract all the compounds that appear in a specific material into a new package.

```

1 from auxi.modelling.process.materials.thermo import Material
2
3 ilmenite = Material("Ilmenite", "./materials/ilmenite.txt")
4 reductant = Material("Reductant", "./materials/reductant.txt")
5 mix = Material("Mix", "./materials/mix.txt")
6
7 ilma_package = ilmenite.create_package("IlmeniteA", 300.0, 1.0, 25.
  ↪0)
8
9 new_package = ilma_package.extract(reductant)
10 print(ilma_package)
11 print(new_package)

```

The existing package loses all the masses of components that appear in the specified material. The new package contains these masses and have the same temperature and pressure as the original material.

```

=====
MaterialPackage
=====
Material          Ilmenite
Mass              2.30038480e+02 kg
Amount           2.99240730e+00 kmol
Pressure          1.00000000e+00 atm
Temperature       2.50000000e+01 °C
Enthalpy          -5.62518853e+02 kWh
-----
Compound Details
Formula           Mass              Mass Fraction    Mole Fraction
-----
Al2O3[S1]         0.00000000e+00    0.00000000e+00    0.00000000e+00
CaO[S]            0.00000000e+00    0.00000000e+00    0.00000000e+00
Cr2O3[S]          2.40500241e-02    1.04547831e-04    5.28784420e-05
Fe2O3[S1]         0.00000000e+00    0.00000000e+00    0.00000000e+00
Fe3O4[S1]         0.00000000e+00    0.00000000e+00    0.00000000e+00
FeO[S]            8.38744589e+01    3.64610559e-01    3.90136068e-01
K2O[S]            1.20250120e-02    5.22739153e-05    4.26611298e-05
MgO[S]            0.00000000e+00    0.00000000e+00    0.00000000e+00
MnO[S]            1.62337662e+00    7.05697857e-03    7.64756215e-03
Na2O[S1]          2.10437710e-02    9.14793518e-05    1.13464164e-04
P4O10[S]          3.00625301e-03    1.30684788e-05    3.53880134e-06
SiO2[S1]          0.00000000e+00    0.00000000e+00    0.00000000e+00
TiO2[S1]          1.43398268e+02    6.23366440e-01    6.00015342e-01
V2O5[S]           1.08225108e+00    4.70465238e-03    1.98848527e-03
=====

=====
MaterialPackage
=====
Material          Reductant

```

Mass	6.99615200e+01	kg	
Amount	5.35762740e-01	kmol	
Pressure	1.00000000e+00	atm	
Temperature	2.50000000e+01	°C	
Enthalpy	-1.25293265e+02	kWh	
-----			
Compound Details			
Formula	Mass	Mass Fraction	Mole Fraction
-----			
C[S1]	0.00000000e+00	0.00000000e+00	0.00000000e+00
H2[G]	0.00000000e+00	0.00000000e+00	0.00000000e+00
O2[G]	0.00000000e+00	0.00000000e+00	0.00000000e+00
N2[G]	0.00000000e+00	0.00000000e+00	0.00000000e+00
S[S1]	0.00000000e+00	0.00000000e+00	0.00000000e+00
Al2O3[S1]	3.48725349e+00	4.98453077e-02	6.38374820e-02
CaO[S]	6.61375661e-02	9.45342042e-04	2.20134358e-03
Fe2O3[S1]	6.07263107e+01	8.67995875e-01	7.09792759e-01
MgO[S]	3.12650313e+00	4.46888965e-02	1.44788444e-01
SiO2[S1]	2.55531506e+00	3.65245789e-02	7.93799718e-02
=====			

## Multiplying a Package by a Scalar

It may sometimes be useful to multiply a package by a scalar.

```

1 from auxi.modelling.process.materials.thermo import Material
2
3 ilmenite = Material("Ilmenite", "./materials/ilmenite.txt")
4 reductant = Material("Reductant", "./materials/reductant.txt")
5 mix = Material("Mix", "./materials/mix.txt")
6
7 ilma_package = ilmenite.create_package("IlmeniteA", 300.0, 1.0, 25.
8     ↪0)
9
10 ilma_package *= 2.0
11 print(ilma_package)

```

This doubles the package mass and enthalpy. Temperature, pressure and composition remain the same, since these are intensive properties.

=====			
MaterialPackage			
=====			
Material	Ilmenite		
Mass	6.00000000e+02	kg	
Amount	7.05634009e+00	kmol	
Pressure	1.00000000e+00	atm	
Temperature	2.50000000e+01	°C	
Enthalpy	-1.37562424e+03	kWh	



-----			
Compound Details			
Formula	Mass	Mass Fraction	Mole Fraction
-----			
Al2O3[S1]	6.97450697e+00	1.16241783e-02	9.69390473e-03
CaO[S]	1.32275132e-01	2.20458554e-04	3.34280337e-04
Cr2O3[S]	4.81000481e-02	8.01667468e-05	4.48486990e-05
Fe2O3[S1]	1.21452621e+02	2.02421036e-01	1.07784066e-01
Fe3O4[S1]	0.00000000e+00	0.00000000e+00	0.00000000e+00
FeO[S]	1.67748918e+02	2.79581530e-01	3.30892788e-01
K2O[S]	2.40500241e-02	4.00833734e-05	3.61829148e-05
MgO[S]	6.25300625e+00	1.04216771e-02	2.19865404e-02
MnO[S]	3.24675325e+00	5.41125541e-03	6.48625791e-03
Na2O[S1]	4.20875421e-02	7.01459035e-05	9.62343053e-05
P4O10[S]	6.01250601e-03	1.00208434e-05	3.00142421e-06
SiO2[S1]	5.11063011e+00	8.51771685e-03	1.20540764e-02
TiO2[S1]	2.86796537e+02	4.77994228e-01	5.08901291e-01
V2O5[S]	2.16450216e+00	3.60750361e-03	1.68652807e-03
=====			

## Setting Package Temperature

Using the “T” property of a `MaterialPackage` object, it is easy to set the temperature of a package to a new value.

```

1 from auxi.modelling.process.materials.thermo import Material
2
3 ilmenite = Material("Ilmenite", "./materials/ilmenite.txt")
4 reductant = Material("Reductant", "./materials/reductant.txt")
5 mix = Material("Mix", "./materials/mix.txt")
6
7 ilma_package = ilmenite.create_package("IlmeniteA", 300.0, 1.0, 25.
8     ↪0)
9
10 ilma_package.T = 1000.0
11 print(ilma_package)

```

This results in the temperature to be updated, as well as the package’s enthalpy.

```

=====
MaterialPackage
=====
Material          Ilmenite
Mass              3.00000000e+02 kg
Amount           3.52817004e+00 kmol
Pressure          1.00000000e+00 atm
Temperature       1.00000000e+03 °C
Enthalpy          -6.18986580e+02 kWh
=====

```

Compound Details			
Formula	Mass	Mass Fraction	Mole Fraction
-----			
Al2O3[S1]	3.48725349e+00	1.16241783e-02	9.69390473e-03
CaO[S]	6.61375661e-02	2.20458554e-04	3.34280337e-04
Cr2O3[S]	2.40500241e-02	8.01667468e-05	4.48486990e-05
Fe2O3[S1]	6.07263107e+01	2.02421036e-01	1.07784066e-01
Fe3O4[S1]	0.00000000e+00	0.00000000e+00	0.00000000e+00
FeO[S]	8.38744589e+01	2.79581530e-01	3.30892788e-01
K2O[S]	1.20250120e-02	4.00833734e-05	3.61829148e-05
MgO[S]	3.12650313e+00	1.04216771e-02	2.19865404e-02
MnO[S]	1.62337662e+00	5.41125541e-03	6.48625791e-03
Na2O[S1]	2.10437710e-02	7.01459035e-05	9.62343053e-05
P4O10[S]	3.00625301e-03	1.00208434e-05	3.00142421e-06
SiO2[S1]	2.55531506e+00	8.51771685e-03	1.20540764e-02
TiO2[S1]	1.43398268e+02	4.77994228e-01	5.08901291e-01
V2O5[S]	1.08225108e+00	3.60750361e-03	1.68652807e-03
=====			

## Setting Package Enthalpy

We can use the “H” property of a `MaterialPackage` object to add or subtract enthalpy, or to set it to a new value. This is very useful when building an energy balance.

```

1 from auxi.modelling.process.materials.thermo import Material
2
3 ilmenite = Material("Ilmenite", "./materials/ilmenite.txt")
4 reductant = Material("Reductant", "./materials/reductant.txt")
5 mix = Material("Mix", "./materials/mix.txt")
6
7 ilma_package = ilmenite.create_package("IlmeniteA", 300.0, 1.0, 25.
8     ↪0)
9
10 ilma_package.H = ilma_package.H + 1.0
11 print(ilma_package)

```

This updates the package’s enthalpy and automatically re-calculates its temperature.

```

=====
MaterialPackage
=====
Material          Ilmenite
Mass              3.00000000e+02 kg
Amount           3.52817004e+00 kmol
Pressure          1.00000000e+00 atm
Temperature       4.22166385e+01 °C
Enthalpy          -6.86812118e+02 kWh
-----
Compound Details

```

Formula	Mass	Mass Fraction	Mole Fraction
Al2O3[S1]	3.48725349e+00	1.16241783e-02	9.69390473e-03
CaO[S]	6.61375661e-02	2.20458554e-04	3.34280337e-04
Cr2O3[S]	2.40500241e-02	8.01667468e-05	4.48486990e-05
Fe2O3[S1]	6.07263107e+01	2.02421036e-01	1.07784066e-01
Fe3O4[S1]	0.00000000e+00	0.00000000e+00	0.00000000e+00
FeO[S]	8.38744589e+01	2.79581530e-01	3.30892788e-01
K2O[S]	1.20250120e-02	4.00833734e-05	3.61829148e-05
MgO[S]	3.12650313e+00	1.04216771e-02	2.19865404e-02
MnO[S]	1.62337662e+00	5.41125541e-03	6.48625791e-03
Na2O[S1]	2.10437710e-02	7.01459035e-05	9.62343053e-05
P4O10[S]	3.00625301e-03	1.00208434e-05	3.00142421e-06
SiO2[S1]	2.55531506e+00	8.51771685e-03	1.20540764e-02
TiO2[S1]	1.43398268e+02	4.77994228e-01	5.08901291e-01
V2O5[S]	1.08225108e+00	3.60750361e-03	1.68652807e-03
=====			

### 3.2.2 Business Modelling

The purpose of this section is to explain a number of concepts and demonstrate the use of the Entity, Component, Activity classes in the auxi.modelling.business module.

#### Basic Activity

A basic activity periodically create a transaction between two specified accounts.

To create an basic activity, import the 'BasicActivity' and the create a 'BasicActivity'

```
from auxi.modelling.business.basic import BasicActivity

basic_activity = BasicActivity("NameA",
                                description="DescriptionA",
                                dt_account="Bank\Default",
                                cr_account="Sales\Default",
                                amount=5000,
                                start=datetime(2016, 2, 1),
                                end=datetime(2017, 2, 1),
                                interval=3)
```



## AUXI REFERENCE

### 4.1 auxi package

#### 4.1.1 Subpackages

**auxi.core package**

**Submodules**

**auxi.core.bibliography module**

**auxi.core.bibliography\_test module**

**auxi.core.helpers module**

This module contains helper functions to ease various tasks.

`auxi.core.helpers.get_date ( date )`

Get the date from a value that could be a date object or a string.

**Parameters** `date` – The date object or string.

**Returns** The date object.

`auxi.core.helpers.get_path_relative_to_module ( module_file_path,  
rela-  
tive_target_path )`

Calculate a path relative to the specified module file.

**Parameters** `module_file_path` – The file path to the module.

**auxi.core.helpers\_test module**

This module contains code used to test core helpers classes.

**class** `auxi.core.helpers_test.HelpersUnitTester` ( *methodName='runTest'* )

Bases: `unittest.case.TestCase`

The unit tester for the helpers functions being tested.

**test\_get\_date** ( )

**test\_get\_path\_relative\_to\_module** ( )

## auxi.core.objects module

**class** `auxi.core.objects.NamedObject` ( *name, description=None* )

Bases: `auxi.core.objects.Object`

Base class for all auxi classes requiring a name and description.

### Parameters

- **name** – the object's name
- **description** – the object's description

**name**

**class** `auxi.core.objects.Object`

Bases: `object`

Base class for all auxi classes.

**read** ( *path* )

**write** ( *path* )

## auxi.core.objects\_test module

This module contains code used to test core object classes.

**class** `auxi.core.objects_test.NamedObjectUnitTester` ( *methodName='runTest'* )

Bases: `unittest.case.TestCase`

The unit tester for the class being tested.

**setUp** ( )

**tearDown** ( )

**test\_\_str\_\_** ( )

Test whether the `__str__` method successfully generates a json string representation of the object.

**test\_constructor** ( )

Test whether the constructor successfully initialises the object.

**class** `auxi.core.objects_test.ObjectUnitTester` ( *methodName='runTest'* )

Bases: `unittest.case.TestCase`

The unit tester for the class being tested.

**setUp** ( )

**tearDown** ( )

**test\_\_str\_\_** ( )

Test whether the \_\_str\_\_ method successfully generates a json string representation of the object.

## auxi.core.reporting module

This module provides classes to create reports.

**class** `auxi.core.reporting. Report` ( *data\_source*, *output\_path=None* )

Bases: `auxi.core.objects.Object`

Base class for all auxi reports.

**render** ( *format=<ReportFormat.printout: (1,)>* )

Render the report in the specified format

**Parameters** **format** – The format. The default format is to print the report to the console.

**Returns** If the format was set to ‘string’ then a string representation of the report is returned.

**class** `auxi.core.reporting. ReportFormat`

Bases: `enum.Enum`

Represents the format the report should be outputted as.

**csv** = `<ReportFormat.csv: (4,>`

**latex** = `<ReportFormat.latex: (2,>`

**matplotlib** = `<ReportFormat.matplotlib: (6,>`

**png** = `<ReportFormat.png: 7>`

**printout** = `<ReportFormat.printout: (1,>`

**string** = `<ReportFormat.string: (5,>`

**txt** = `<ReportFormat.txt: (3,>`

## auxi.core.reporting\_test module

This module contains code used to test core reporting classes.

**class** `auxi.core.reporting_test. ReportingUnitTester` ( *methodName='runTest'* )

Bases: `unittest.case.TestCase`

The unit tester for the class being tested.

**setUp ( )**

**tearDown ( )**

**test\_render\_with\_file ( )**

Test whether a value is returned when a report is rendered in a string format. And whether any of the other formats throw an error.

**test\_render\_without\_file ( )**

Test whether a value is returned when a report is rendered in a string format. And whether any of the other formats throw an error.

## auxi.core.time module

This module provides classes to manage time.

```
class auxi.core.time. Clock ( name,                                     description=None,
                                start_datetime=datetime.datetime(1, 1, 1, 0, 0),
                                timestep_period_duration=<TimePeriod.month:
                                7>, timestep_period_count=1)
```

Bases: *auxi.core.objects.NamedObject*

Represents a clock that provides functions to manage a ticking clock based on a time period as well as retrieve the current tick's date since the start date.

**get\_datetime ( )**

Get the clock's current datetime.

**Returns** The datetime.

**get\_datetime\_at\_period\_ix ( ix)**

Get the datetime at a given period.

**Parameters period** – The index of the period.

**Returns** The datetime.

**reset ( )**

Resets the clock's timestep index to '0'.

**tick ( )**

Increment the clock's timestep index.

```
class auxi.core.time. TimePeriod
```

Bases: *enum.Enum*

Represents a period in time.

**day = <TimePeriod.day: 5>**

**hour = <TimePeriod.hour: 4>**

**millisecond = <TimePeriod.millisecond: 1>**

**minute = <TimePeriod.minute: 3>**

**month = <TimePeriod.month: 7>**



```
second = <TimePeriod.second: 2>
week   = <TimePeriod.week: 6>
year   = <TimePeriod.year: 8>
```

## auxi.core.time\_test module

This module provides testing code for the auxi.core.time module.

```
class auxi.core.time_test.ClockUnitTester ( methodName='runTest')
    Bases: unittest.case.TestCase

    Tester for the auxi.core.time.Clock class.

    setUp ( )
    test_constructor ( )
    test_get_datetime ( )
    test_get_datetime_at_period_ix ( )
    test_reset ( )
    test_tick ( )
```

## Module contents

This package contains foundational infrastructure classes and functions that are used throughout the rest of auxi.

## auxi.modelling package

### Subpackages

#### auxi.modelling.business package

### Submodules

#### auxi.modelling.business.basic module

This module provides class and functions for basic business activities.

```
class auxi.modelling.business.basic. BasicActivity ( name,
                                                    dt_account,
                                                    cr_account,
                                                    amount=0,
                                                    start=datetime.datetime(1,
1, 1, 0, 0),
                                                    end=datetime.datetime(9999,
12, 31, 23, 59,
59, 999999),
                                                    interval=1,
                                                    description=None)
```

Bases: `auxi.modelling.business.structure.Activity`

An activity class that provides the most basic activity functionality: periodically create a transaction between two specified accounts.

#### Parameters

- **name** – The name.
- **dt\_account** – The debit account.
- **cr\_account** – The credit account.
- **amount** – The amount of an activity.
- **start** – The datetime the activity should be started.
- **end** – The datetime the activity should be run until.
- **interval** – The interval of the activity.
- **description** – The description.

**get\_referenced\_accounts** ( )

Retrieve the general ledger accounts referenced in this instance.

**Returns** The referenced accounts.

**run** ( *clock*, *generalLedger* )

Execute the activity at the current clock cycle.

#### Parameters

- **clock** – The clock containing the current execution time and period information.
- **generalLedger** – The general ledger into which to create the transactions.

```
class auxi.modelling.business.basic. BasicLoanActivity ( name,
                                                         bank_account,
                                                         loan_account,
                                                         inter-
                                                         est_account,
                                                         amount=0,
                                                         inter-
                                                         est_rate=0.0,
                                                         start=datetime.datetime(1,
                                                         1, 1, 0,
                                                         0),
                                                         dura-
                                                         tion=60,
                                                         inter-
                                                         val=1,
                                                         descrip-
                                                         tion=None)
```

Bases: `auxi.modelling.business.structure.Activity`

An activity class that provides the most basic activity functionality for a loan: Creates a loan transaction and periodically create transactions to consider the interest and to pay the interest.

#### Parameters

- **name** – The name.
- **description** – The description.
- **bank\_account** – The asset account that is increased.
- **loan\_account** – The liability account that is decreased.
- **interest\_account** – The expense account the interest is added to.
- **amount** – The loan amount. The default amount is 0
- **interest\_rate** – The interest rate as a fraction of the whole (e.g. 0.15 = 15%). The default value is 0.0
- **start** – The datetime the activity should be started.
- **duration** – The duration of the loan in months.
- **interval** – The interval of the activity.

**amount**

**get\_referenced\_accounts** ( )

Retrieve the general ledger accounts referenced in this instance.

**Returns** The referenced accounts.

**interest\_rate**

**prepare\_to\_run** ( *clock*, *period\_count* )

Prepare the activity for execution.

#### Parameters

- **clock** – The clock containing the execution start time and execution period information.
- **period\_count** – The total amount of periods this activity will be requested to be run for.

**run** ( *clock*, *generalLedger* )

Execute the activity at the current clock cycle.

#### Parameters

- **clock** – The clock containing the current execution time and period information.
- **generalLedger** – The general ledger into which to create the transactions.

## auxi.modelling.business.basic\_test module

This module provides testing code for the auxi.modelling.business.basic module.

**class** auxi.modelling.business.basic\_test. **BasicActivityUnitTester** ( *methodName*  
Bases: unittest.case.TestCase

Tester for the auxi.modelling.business.basic.BasicActivity class.

**setUp** ( )

**test\_meet\_exection\_criteria** ( )

Test that the activity only meets the execution criteria when it's amount is greater than 0.

**test\_constructor** ( )

**test\_get\_referenced\_accounts** ( )

Test that the activity run method get\_referenced\_accounts accounts matches the debit and credit accounts self.object was initialised with.

**test\_run** ( )

Test that the activity run method creates a transaction with an amount of 5000.

**class** auxi.modelling.business.basic\_test. **BasicLoanActivityUnitTester** ( *methodName*  
Bases: unittest.case.TestCase

Tester for the auxi.modelling.business.basic.BasicLoanActivity class.

**setUp** ( )

**test\_meet\_exection\_criteria** ( )

Test that the activity only meets the execution criteria when it's amount is greater than 0 and its duration is greater than 0.

**test\_constructor ( )**

**test\_get\_referenced\_accounts ( )**

Test that the activity run method `get_referenced_accounts` accounts matches the debit and credit accounts `self.object` was initialised with.

**test\_run\_first\_month ( )**

Test that the activity run method creates a transaction with an amount of 180000 on the first month. No other transactions

**test\_run\_last\_month ( )**

Test that the activity run method creates settled the loan on the loans' last month and that the transactions

**test\_run\_third\_month ( )**

Test that the activity run method accrued the interest correctly.

## auxi.modelling.business.models module

This module provides classes to work with business models.

```
class auxi.modelling.business.models. TimeBasedModel ( name,
                                                         descrip-
                                                         tion=None,
                                                         start_datetime=datetime.datetime
                                                         7, 21, 14,
                                                         2,      48,
                                                         626911),
                                                         pe-
                                                         riod_duration=<TimePeriod.yea
                                                         8>,      pe-
                                                         riod_count=1)
```

Bases: *auxi.core.objects.NamedObject*

Represents an time based model class. An instance of this class is by default configured to run only once, thus functioning as a steady state model. The instance's time based parameters must be configured for it to function as a time based model.

### Parameters

- **name** – The name.
- **description** – The description.
- **start\_datetime** – The start datetime of the model.
- **period\_duration** – The duration of the model's time period. e.g. month, day etc.
- **period\_count** – The number of periods to execute the model for.

**create\_entity ( name, gl\_structure, description=None )**

Create an entity and add it to the model.

### Parameters

- **name** – The entity name.
- **gl\_structure** – The entity’s general ledger structure.
- **description** – The entity description.

**Returns** The created entity.

**name**

**prepare\_to\_run ( )**

Prepare the model for execution.

**remove\_entity ( name )**

Remove an entity from the model.

**Parameters name** – The name of the entity to remove.

**run ( )**

Execute the model.

## auxi.modelling.business.models\_test module

This module provides testing code for the classes in the auxi.modelling.business.models module.

```
class auxi.modelling.business.models_test. TimeBasedModelUnitTester ( methodNa
    Bases: unittest.case.TestCase
```

Tester for the auxi.modelling.business.models.TimeBasedModel class.

**setUp ( )**

**test\_constructor ( )**

**test\_create\_entity ( )**

**test\_prepare\_to\_run ( )**

Test that the model’s entities prepare\_to\_run is called when the model’s prepare\_to\_run is called.

**test\_remove\_entity ( )**

**test\_run ( )**

Test that the model’s entities run is called when the model’s run is called. Also test that the model was run for the expected timeperiod.

**test\_set\_name ( )**

Test whether the name changes when it is set, that the model’s path is updated and that the model’s children’s paths are updated correctly.

## auxi.modelling.business.structure module

This module provides an classes used to create a business structure.

```
class auxi.modelling.business.structure. Activity ( name,
                                                    start=datetime.datetime(1,
1, 1, 0, 0),
                                                    end=datetime.datetime(9999,
12, 31, 23, 59,
59, 999999),
                                                    interval=1,
                                                    descrip-
                                                    tion=None)
```

Bases: *auxi.core.objects.NamedObject*

Represents an activity base class. An activity will typically represent a transaction activity in a business.

### Parameters

- **name** – The name.
- **description** – The description.
- **start** – The datetime the activity should be started.
- **end** – The datetime the activity should be run until.
- **interval** – The interval of the activity.

```
get_referenced_accouts ( )
```

Retrieve the general ledger accounts referenced in this instance.

**Returns** The referenced accounts.

**name**

```
prepare_to_run ( clock, period_count)
```

Prepare the activity for execution.

### Parameters

- **clock** – The clock containing the execution start time and execution period information.
- **period\_count** – The total amount of periods this activity will be requested to be run for.

```
set_parent_path ( value)
```

Set the parent path and the path from the new parent path.

**Parameters** **value** – The path to the object's parent

```
class auxi.modelling.business.structure. Component ( name,      gl,
                                                    descrip-
                                                    tion=None)
```

Bases: *auxi.core.objects.NamedObject*

Represents an component class. A component class that represents a component of an entity. A component has business activities

**Parameters**

- **name** – The name.
- **description** – The description.

**add\_activity** ( *activity* )

Add an activity to the component.

**Parameters** **activity** – The activity.

**create\_component** ( *name, description=None* )

Create a sub component in the business component.

**Parameters**

- **name** – The new component's name.
- **description** – The new component's description.

**Returns** The created component.

**get\_activity** ( *name* )

Retrieve an activity given its name.

**Parameters** **name** – The name of the activity.

**Returns** The activity.

**get\_component** ( *name* )

Retrieve a child component given its name.

**Parameters** **name** – The name of the component.

**Returns** The component.

**name**

**prepare\_to\_run** ( *clock, period\_count* )

Prepare the component for execution.

**Parameters**

- **clock** – The clock containing the execution start time and execution period information.
- **period\_count** – The total amount of periods this activity will be requested to be run for.

**remove\_component** ( *name* )

Remove a sub component from the component.

**Parameters** **name** – The name of the component to remove.

**run** ( *clock, generalLedger* )

Execute the component at the current clock cycle.



### Parameters

- **clock** – The clock containing the current execution time and period information.
- **generalLedger** – The general ledger into which to create the transactions.

**set\_parent\_path** ( *value* )

Set the parent path and the path from the new parent path.

**Parameters value** – The path to the object's parent.

**class** `auxi.modelling.business.structure.Entity` ( *name*,  
*gl\_structure*, *description=None*

Bases: `auxi.core.objects.NamedObject`

Represents an entity class. An entity consists of business components e.g. Sales department. It executes its components and performs financial year end transactions.

### Parameters

- **name** – The name.
- **gl\_structure** – The general ledger structure the entity's general ledger will be initialized with.
- **description** – The description.
- **period\_count** – The number of periods the entity should be run for.

**create\_component** ( *name*, *description=None* )

Create a component in the business entity.

### Parameters

- **name** – The component's name.
- **description** – The component's description.

**Returns** The created component.

**name**

**prepare\_to\_run** ( *clock*, *period\_count* )

Prepare the entity for execution.

### Parameters

- **clock** – The clock containing the execution start time and execution period information.
- **period\_count** – The total amount of periods this activity will be requested to be run for.

**remove\_component** ( *name* )

Remove a component from the entity.

**Parameters name** – The name of the component to remove.

**run** ( *clock* )

Execute the entity at the current clock cycle.

**Parameters clock** – The clock containing the current execution time and period information.

**set\_parent\_path** ( *value* )

Set the parent path and the path from the new parent path.

**Parameters value** – The path to the object's parent

## auxi.modelling.business.structure\_test module

This module provides testing code for the auxi.modelling.business.activity module.

@author: Ex Mente Technologies (Pty) Ltd

```
class auxi.modelling.business.structure_test. ActivityUnitTester ( methodName=  
    Bases: unittest.case.TestCase
```

Tester for the auxi.modelling.business.structure.Activity class.

```
    setUp ( )
```

```
    test__meet_exection_criteria ( )
```

```
    test_constructor ( )
```

```
    test_get_path ( )
```

```
    test_get_referenced_accounts ( )
```

```
    test_prepare_to_run ( )
```

```
    test_set_name ( )
```

Test wether the name changes when it is set and that the activity's path is updated correctly.

```
    test_set_parent_path ( )
```

```
class auxi.modelling.business.structure_test. ComponentUnitTester ( methodName=  
    Bases: unittest.case.TestCase
```

Tester for the auxi.modelling.business.structure.Component class.

```
    setUp ( )
```

```
    test_add_activity_invalid_account_name ( )
```

```
    test_add_activity_valid_account_name ( )
```

```
    test_constructor ( )
```

```
    test_create_component ( )
```

```
    test_get_activity_exists ( )
```

**test\_get\_activity\_not\_exists ( )**

**test\_get\_component\_exists ( )**

**test\_get\_component\_not\_exists ( )**

**test\_prepare\_to\_run ( )**

Test that the component run's its activities' prepare\_to\_run methods.

**test\_remove\_component ( )**

**test\_run ( )**

Test that the component runs its activities.

**test\_set\_name ( )**

Test whether the name changes when it is set, that the component's name changes and that the component's children's paths are updated correctly.

**test\_set\_parent\_path ( )**

**class** auxi.modelling.business.structure\_test. **EntityUnitTester** ( *methodName='run'*  
Bases: unittest.case.TestCase

Tester for the auxi.modelling.entity.component class.

**setUp ( )**

**test\_\_perform\_year\_end\_gross\_profit ( )**

Test that the year end gross profit account is closed correctly.

**test\_\_perform\_year\_end\_gross\_profit\_and\_income\_summary ( )**

Test that the year end gross profit and income summary accounts are summed up correctly.

**test\_\_perform\_year\_end\_income\_summary ( )**

Test that the year end income summary account is closed correctly.

**test\_\_perform\_year\_end\_income\_tax ( )**

**test\_\_perform\_year\_end\_procedure ( )**

Test that all the year end accounts has been closed of correctly.

**test\_\_perform\_year\_end\_retained\_earnings ( )**

Test that the year end retained earnings account is closed correctly.

**test\_constructor ( )**

**test\_create\_component ( )**

**test\_getitem\_exists ( )**

**test\_getitem\_not\_exists ( )**

**test\_prepare\_to\_run ( )**

Test that the entity run's its component' prepare\_to\_run methods.

**test\_remove\_component ( )**

**test\_run ( )**

Test that the entity runs its components.

**test\_set\_name ( )**

Test whether the name changes when it is set, that the entity's name changes and that the component's children's paths are updated correctly.

**test\_set\_parent\_path ( )**

## Module contents

auxi.modelling.business Package

The purpose of this package is to provide common classes and functions for the auxi.modelling.business namespace

## auxi.modelling.financial package

### Submodules

#### auxi.modelling.financial.des module

This module provides classes representing the accounting double entry system.

auxi.modelling.financial.des. **AT**

alias of AccountType

**class** auxi.modelling.financial.des. **AccountType**

Bases: enum.Enum

Represents the type of general ledger account.

**asset** = <AccountType.asset: 1>

**equity** = <AccountType.equity: 2>

**expense** = <AccountType.expense: 3>

**liability** = <AccountType.liability: 4>

**revenue** = <AccountType.revenue: 5>

**class** auxi.modelling.financial.des. **GeneralLedger** ( *name*, *structure*, *description*=None)

Bases: *auxi.core.objects.NamedObject*

Represents the account structure of a general ledger.

#### Parameters

- **name** – The name.
- **structure** – The general ledger structure.

- **description** – The description.

**balance\_sheet** ( *end=datetime.datetime(9999, 12, 31, 23, 59, 59, 999999)*, *format=<ReportFormat.printout: (1, )>*, *output\_path=None*)

Generate a transaction list report.

#### Parameters

- **end** – The end date to generate the report for.
- **format** – The format of the report.
- **output\_path** – The path to the file the report is written to. If None, then the report is not written to a file.

**Returns** The generated report.

**create\_transaction** ( *name*, *description=None*, *tx\_date=datetime.date(1, 1, 1)*, *dt\_account=None*, *cr\_account=None*, *source=None*, *amount=0.0*)

Create a transaction in the general ledger.

#### Parameters

- **name** – The transaction's name.
- **description** – The transaction's description.
- **tx\_date** – The date of the transaction.
- **cr\_account** – The transaction's credit account's name.
- **dt\_account** – The transaction's debit account's name.
- **source** – The name of source the transaction originated from.
- **amount** – The transaction amount.

**Returns** The created transaction.

**income\_statement** ( *start=datetime.datetime(1, 1, 1, 0, 0)*, *end=datetime.datetime(9999, 12, 31, 23, 59, 59, 999999)*, *format=<ReportFormat.printout: (1, )>*, *component\_path=''*, *output\_path=None*)

Generate a transaction list report.

#### Parameters

- **start** – The start date to generate the report for.
- **end** – The end date to generate the report for.
- **format** – The format of the report.
- **component\_path** – The path of the component to filter the report's transactions by.
- **output\_path** – The path to the file the report is written to. If None, then the report is not written to a file.

**Returns** The generated report.

```
transaction_list ( start=datetime.datetime(1, 1, 1, 0, 0),  
                    end=datetime.datetime(9999, 12, 31, 23, 59, 59,  
                    999999), format=<ReportFormat.printout: (1, )>,  
                    component_path='', output_path=None)
```

Generate a transaction list report.

#### Parameters

- **start** – The start date to generate the report for.
- **end** – The end date to generate the report for.
- **format** – The format of the report.
- **component\_path** – The path of the component to filter the report's transactions by.
- **output\_path** – The path to the file the report is written to. If None, then the report is not written to a file.

**Returns** The generated report.

```
class auxi.modelling.financial.des. GeneralLedgerAccount ( name,  
                                                            de-  
                                                            scrip-  
                                                            tion=None,  
                                                            num-  
                                                            ber=None,  
                                                            ac-  
                                                            count_type=<AccountType  
                                                            5>)
```

Bases: *auxi.core.objects.NamedObject*

Represents an account of a general ledger.

#### Parameters

- **name** – The name.
- **description** – The description.
- **number** – The number.
- **account\_type** – The type of account.

```
create_account ( name, number=None, description=None)
```

Create a sub account in the account.

#### Parameters

- **name** – The account name.
- **description** – The account description.
- **number** – The account number.

**Returns** The created account.

**get\_child\_account** ( *account\_name* )

Retrieves a child account. This could be a descendant nested at any level.

**Parameters** **account\_name** – The name of the account to retrieve.

**Returns** The child account, if found, else None.

**name**

**remove\_account** ( *name* )

Remove an account from the account's sub accounts.

**Parameters** **name** – The name of the account to remove.

**set\_parent\_path** ( *value* )

Set the parent path and the path from the new parent path.

**Parameters** **value** – The path to the object's parent

**class** `auxi.modelling.financial.des.GeneralLedgerStructure` ( *name*,  
*de-*  
*scrip-*  
*tion=None* )

Bases: `auxi.core.objects.NamedObject`

The account structure of a general ledger.

**Parameters**

- **name** – The name.
- **description** – The description.

**get\_account** ( *account\_name* )

Retrieves an account from the general ledger structure given the account name.

**Parameters** **account\_name** – The account name.

**Returns** The requested account, if found, else None.

**get\_account\_descendants** ( *account* )

Retrieves an account's descendants from the general ledger structure given the account name.

**Parameters** **account\_name** – The account name.

**Returns** The descendants of the account.

**report** ( *format=<ReportFormat.printout: (1, )>*, *output\_path=None* )

Returns a report of this class.

**Parameters**

- **format** – The format of the report.
- **output\_path** – The path to the file the report is written to. If None, then the report is not written to a file.

**Returns** The descendants of the account.

**validate\_account\_names** ( *names* )

Validates whether the accounts in a list of account names exists.

**Parameters** **names** – The names of the accounts.

**Returns** The descendants of the account.

```
class auxi.modelling.financial.des. Transaction ( name,      descrip-
                                                    tion=None,
                                                    tx_date=datetime.date(1,
                                                                    1,
                                                                    1),
                                                    dt_account=None,
                                                    cr_account=None,
                                                    source=None,
                                                    amount=0.0,
                                                    is_closing_dt_account=False,
                                                    is_closing_cr_account=False)
```

Bases: *auxi.core.objects.NamedObject*

Represents a financial transaction between two general ledger accounts.

#### Parameters

- **name** – The name.
- **description** – The description.
- **tx\_date** – The transaction's date.
- **dt\_account** – The account to debit.
- **cr\_account** – The account to credit.
- **source** – The source that created the transaction.
- **amount** – The transaction's amount.
- **is\_closing\_dt\_account** – Specifies whether this is a closing debit account.
- **is\_closing\_cr\_account** – Specifies whether this is a closing credit account.

```
class auxi.modelling.financial.des. TransactionTemplate ( name,
                                                            dt_account,
                                                            cr_account,
                                                            de-
                                                            scrip-
                                                            tion=None)
```

Bases: *auxi.core.objects.NamedObject*

Represents a template for how a transaction is to be created.

#### Parameters

- **name** – The name of the transaction.
- **description** – The description of the transaction.



- **dt\_account** – The account to debit.
- **cr\_account** – The account to credit.

## auxi.modelling.financial.des\_test module

This module provides testing code for the auxi.modelling.financial.des module.

```
class auxi.modelling.financial.des_test. GeneralLedgerAccountUnitTester ( method
    Bases: unittest.case.TestCase
```

Tester for the auxi.modelling.financial.des.GeneralLedgerAccount class.

```
    setUp ( )
```

```
    test_constructor ( )
```

```
    test_create_account ( )
```

```
    test_get_child_account ( )
```

```
    test_remove_account ( )
```

```
    test_set_parent_path ( )
```

```
class auxi.modelling.financial.des_test. GeneralLedgerStructureUnitTester ( m
    Bases: unittest.case.TestCase
```

Tester for the auxi.modelling.financial.des.generalledgerstructure class.

```
    setUp ( )
```

```
    test_constructor ( )
```

Test the the variables has been initialised and that the default accounts has been created.

```
    test_get_account ( )
```

```
    test_get_account_decendants ( )
```

```
    test_report ( )
```

```
    test_validate_account_name_invalid ( )
```

```
    test_validate_account_name_valid ( )
```

```
class auxi.modelling.financial.des_test. GeneralLedgerUnitTester ( methodName=
    Bases: unittest.case.TestCase
```

Tester for the auxi.modelling.financial.des.GeneralLedger class.

```
    setUp ( )
```

```
    test_constructor ( )
```

```
    test_create_transaction ( )
```

```
class auxi.modelling.financial.des_test. TransactionTemplateUnitTester ( method
    Bases: unittest.case.TestCase

    Tester for the auxi.modelling.financial.des.TransactionTemplate class.

    setUp ( )

    test_constructor ( )

class auxi.modelling.financial.des_test. TransactionUnitTester ( methodName='ru
    Bases: unittest.case.TestCase

    Tester for the auxi.modelling.financial.des.Transaction class.

    setUp ( )

    test_constructor ( )
```

## auxi.modelling.financial.reporting module

This module provides classes to manage currencies.

```
class auxi.modelling.financial.reporting. BalanceSheet ( data_source,
                                                            end=datetime.date(9999,
                                                            12, 31),
                                                            out-
                                                            put_path=None)

    Bases: auxi.modelling.financial.reporting.Report

    Report a balance sheet of a general ledger.

    Parameters

    • data_source – The object to report on.

    • end – The end date to generate the report for.

    • output_path – The path to write the report file to.

class auxi.modelling.financial.reporting. GeneralLedgerStructure ( data_source,
                                                                    out-
                                                                    put_path=None)

    Bases: auxi.modelling.financial.reporting.Report

    Report on a general ledger structure.

    Parameters

    • data_source – The object to report on.

    • output_path – The path to write the report file to.
```

```
class auxi.modelling.financial.reporting. IncomeStatement ( data_source,
                                                             start=datetime.date(1,
                                                             1,
                                                             1),
                                                             end=datetime.date(9999,
                                                             12,
                                                             31),
                                                             com-
                                                             po-
                                                             nent_path='',
                                                             out-
                                                             put_path=None)
```

Bases: `auxi.modelling.financial.reporting.Report`

Report an income statement of a general ledger.

#### Parameters

- **data\_source** – The object to report on.
- **end** – The start date to generate the report for.
- **end** – The end date to generate the report for.
- **component\_path** – The path of the component to filter the report's transactions by.
- **output\_path** – The path to write the report file to.

```
class auxi.modelling.financial.reporting. Report ( data_source, out-
                                                             put_path=None)
```

Bases: `auxi.core.reporting.Report`

Base class for reports.

#### Parameters

- **data\_source** – The object to report on.
- **output\_path** – The path to write the report file to.

```
class auxi.modelling.financial.reporting. ReportType
```

Bases: `enum.Enum`

Represents a report type, e.g. balance sheet or income statement.

**balance\_sheet** = <ReportType.balance\_sheet: (1,>

**cash\_flow** = <ReportType.cash\_flow: 4>

**income\_statement** = <ReportType.income\_statement: (2,>

**transaction\_list** = <ReportType.transaction\_list: (3,>

```
class auxi.modelling.financial.reporting. TransactionList ( data_source,
                                                             start=datetime.date(1,
                                                             1,
                                                             1),
                                                             end=datetime.date(9999,
                                                             12,
                                                             31),
                                                             com-
                                                             po-
                                                             nent_path='',
                                                             out-
                                                             put_path=None)
```

Bases: `auxi.modelling.financial.reporting.Report`

Report on a list of transactions.

#### Parameters

- **data\_source** – The object to report on.
- **end** – The start date to generate the report for.
- **end** – The end date to generate the report for.
- **component\_path** – The path of the component to filter the report's transactions by.
- **output\_path** – The path to write the report file to.

### auxi.modelling.financial.reporting\_test module

This module provides testing code for the `auxi.modelling.financial.des` module.

```
class auxi.modelling.financial.reporting_test. GeneralLedgerStructureUnitTes
Bases: unittest.case.TestCase
```

Tester for the `auxi.modelling.financial.reporting.GeneralLedgerStructure` class.

```
setUp ( )
```

```
test__generate_table__ ( )
```

```
class auxi.modelling.financial.reporting_test. TransactionListUnitTester ( me
Bases: unittest.case.TestCase
```

Tester for the `auxi.modelling.financial.reporting.TransactionList` class.

```
setUp ( )
```

```
test__generate_table__ ( )
```

### Module contents

`auxi.modelling.financial` Package

The purpose of this package is to provide common classes and functions for the the `auxi.modelling.financial` namespace

## auxi.modelling.process package

### Subpackages

## auxi.modelling.process.materials package

### Submodules

## auxi.modelling.process.materials.chem module

This module provides classes to work with materials and material packages that are described with chemical compositions.

```
class auxi.modelling.process.materials.chem. Material ( name,
                                                    file_path,
                                                    description=None)
```

Bases: `auxi.core.objects.NamedObject`

A material consisting of multiple chemical compounds.

#### Parameters

- **name** – The material's name.
- **file\_path** – The path of the material definition file.
- **description** – the material's description

The format of the text file is as follows:

- The lines are space separated. The values in a line are separated by one or more spaces.
- The first line is a heading line.
- All subsequent lines contain a compound formula, followed by mass fractions.
- The first column lists the compounds in the material.
- All subsequent columns describe assays of the material.

The following is an example of a material text file:

Compound	IlmeniteA	IlmeniteB	IlmeniteC
Al2O3	0.01160	0.01550	0.00941
CaO	0.00022	0.00001	0.00017
Cr2O3	0.00008	0.00022	0.00011
Fe2O3	0.20200	0.47300	0.49674
Fe3O4	0.00000	0.00000	0.00000

FeO	0.27900	0.19100	0.00000
K2O	0.00004	0.00001	0.00005
MgO	0.01040	0.00580	0.01090
MnO	0.00540	0.00480	0.00525
Na2O	0.00007	0.00005	0.00031
P4O10	0.00001	0.00032	0.00015
SiO2	0.00850	0.00490	0.01744
TiO2	0.47700	0.29400	0.45949
V2O5	0.00360	0.00800	0.00000

**add\_assay** ( *name*, *assay* )

Add an assay to the material.

**Parameters**

- **name** – The name of the new assay.
- **assay** – A list containing the compound mass fractions for the assay. The sequence of the assay's elements must correspond to the sequence of the material's compounds.

**create\_empty\_assay** ( )

Create an empty array to store an assay. The array's length will be equal to the number of compounds in the material.

**Returns** A floating point array.

**create\_package** ( *assay=None*, *mass=0.0*, *normalise=True* )

Create a MaterialPackage based on the specified parameters.

**Parameters**

- **assay** – The name of the assay based on which the package must be created.
- **mass** – [kg] The mass of the package.
- **normalise** – Indicates whether the assay must be normalised before creating the package.

**Returns** The created MaterialPackage.

**get\_assay\_total** ( *name* )

Calculate the total of the specified assay.

**Parameters** **name** – The name of the assay.

**Returns** The total mass fraction of the specified assay.

**get\_compound\_index** ( *compound* )

Determine the index of the specified compound.

**Parameters** **compound** – The formula and phase of the specified compound, e.g. 'Fe2O3[S1]'.

**Returns** The index of the specified compound.

**class** auxi.modelling.process.materials.chem. **MaterialPackage** ( *material*,  
*compound\_masses* )

Bases: *auxi.core.objects.Object*

A package of a material consisting of multiple chemical compounds.

#### Parameters

- **material** – A reference to the Material to which self belongs.
- **compound\_masses** – [kg] The masses of the compounds in the package.

**add\_to** ( *other* )

Add another chem material package to this material package.

**Parameters** *other* – The other material package.

**clear** ( )

Set all the compound masses in the package to zero.

**clone** ( )

Create a complete copy of self.

**Returns** A MaterialPackage that is identical to self.

**extract** ( *other* )

Extract ‘other’ from self, modifying self and returning the extracted material as a new package.

**Parameters** *other* – Can be one of the following:

- float: A mass equal to other is extracted from self. Self is reduced by other and the extracted package is returned as a new package.
- tuple (compound, mass): The other tuple specifies the mass of a compound to be extracted. It is extracted from self and the extracted mass is returned as a new package.
- string: The ‘other’ string specifies the compound to be extracted. All of the mass of that compound will be removed from self and a new package created with it.

**Returns** A new material package containing the material that was extracted from self.

**get\_assay** ( )

Determine the assay of self.

**Returns** [mass fractions] An array containing the assay of self.

**get\_compound\_mass** ( *compound* )

Get the mass of the specified compound in the package.

**Parameters** *compound* – The formula of the compound, e.g. Fe<sub>2</sub>O<sub>3</sub>.

**Returns** [kg]

**get\_compound\_mass\_fraction** ( *compound* )

Get the mass fraction of the specified compound in self.

**Parameters** **compound** – The formula and phase of the compound, e.g. Fe2O3.

**Returns** []

**get\_element\_mass** ( *element* )

Determine the masses of elements in the package.

**Returns** [kg] An array of element masses. The sequence of the elements in the result corresponds with the sequence of elements in the element list of the material.

**get\_element\_mass\_dictionary** ( )

Determine the masses of elements in the package and return as a dictionary.

**Returns** [kg] A dictionary of element symbols and masses.

**get\_element\_masses** ( )

Get the masses of elements in the package.

**Returns** [kg] An array of element masses. The sequence of the elements in the result corresponds with the sequence of elements in the element list of the material.

**get\_mass** ( )

Get the mass of the package.

**Returns** [kg]

## auxi.modelling.process.materials.chem\_test module

This module provides testing code for classes in the chem module.

**class** auxi.modelling.process.materials.chem\_test. **ChemMaterialPackageUnitTes**

Bases: unittest.case.TestCase

Tester for the auxi.modelling.process.materials.chemistry.material.Material class.

**add\_incompatible\_packages** ( )

**setUp** ( )

**test\_add\_operator\_1** ( )

other = MaterialPackage

Test whether the add operator calculates the resulting package correctly. Results were checked against FactSage results. They are not exactly the same, since the magnetic and other non-cp contributions are omitted by the thermo module.

**test\_add\_operator\_2** ( )

Tests the scenario when a ‘mix’ is created and two packages ‘mixed’ into the mix package.



```

test_add_operator_3 ( )
    other = tuple (compound, mass) Test whether the add operator calculates the result-
    ing package correctly. Results were checked against FactSage results. They are not
    exactly the same, since the magnetic and other non-cp contributions are omitted by
    the thermo module.

test_clone ( )

test_constructor ( )

test_extract_1 ( )

test_get_assay ( )

test_get_compound_mass ( )

test_get_element_masses ( )

test_get_mass ( )

test_multiply_operator ( )

test_subtract_operator_2 ( )

test_subtract_operator_3 ( )

class auxi.modelling.process.materials.chem_test. ChemMaterialUnitTester ( me
    Bases: unittest.case.TestCase

    Tester for the auxi.modelling.process.materials.chem.Material class.

    assertAlmostEqual ( first, second, places=14, msg=None, delta=None)

    setUp ( )

    test_add_assay ( )

    test_constructor ( )

    test_create_empty_assay ( )

    test_create_package ( )

    test_get_assay_total ( )

    test_get_compound_index ( )

```

## auxi.modelling.process.materials.core module

This module provides a material class that can do thermochemical calculations.

```

class auxi.modelling.process.materials.core. Material ( name,
                                                         state_of_matter=<StateOfMatter
                                                         0>, prop-
                                                         erty_models=None,
                                                         descrip-
                                                         tion=None)

    Bases: auxi.core.objects.NamedObject

```

Represents a material consisting of multiple chemical compounds, having the ability to do thermochemical calculations.

**Parameters**

- **name** – A name for the material.
- **state\_of\_matter** – The material's state of matter, e.g. liquid.
- **file\_path** – The location of the file containing the material's data.
- **description** – the material's description

**Cp** ( *\*\*state* )

Calculate the Cp value given the material state.

**Parameters** **\*\*state** – material state

**Returns** float

**alpha** ( *\*\*state* )

Calculate the alpha value given the material state.

**Parameters** **\*\*state** – material state

**Returns** float

**beta** ( *\*\*state* )

Calculate the alpha value given the material state.

**Parameters** **\*\*state** – material state

**Returns** float

**k** ( *\*\*state* )

Calculate the k value given the material state.

**Parameters** **\*\*state** – material state

**Returns** float

**mstate** = None

State of matter.

**mu** ( *\*\*state* )

Calculate the mu value given the material state.

**Parameters** **\*\*state** – material state

**Returns** float

**nu** ( *\*\*state* )

Calculate the nu value given the material state.

**Parameters** **\*\*state** – material state

**Returns** float

**rho** ( *\*\*state* )

Calculate the rho value given the material state.

**Parameters** **\*\*state** – material state

**Returns** float

### auxi.modelling.process.materials.core\_test module

This module provides testing code for classes in the chem module.

**class** `auxi.modelling.process.materials.core_test.MaterialTester` ( *methodName=*  
Bases: `unittest.case.TestCase`

Tester for the `auxi.modelling.process.materials.core.Material` class.

**test\_beta** ( )

**test\_constructor** ( )

### auxi.modelling.process.materials.psd module

This module provides psd material and material package classes that can do size distribution calculations.

**class** `auxi.modelling.process.materials.psd.Material` ( *name,*  
*file\_path,*  
*description=None*)

Bases: `auxi.core.objects.NamedObject`

Represents a particulate material consisting of multiple particle size classes.

#### Parameters

- **name** – The material's name.
- **file\_path** – The path of the material definition file.
- **description** – the material's description

The format of the text file is as follows:

- The lines are space separated. The values in a line are separated by one or more spaces.
- The first line is a heading line.
- All subsequent lines contain a particle size, followed by mass fractions.
- Particle sizes are indicated in [meter].
- The first column lists the particle sizes in the material. Each class must be interpreted as “mass fraction retained”. In other words if the size class is indicated as 307.2E-3, it means that it is the class of material retained on a 307.2mm screen, and can also be thought of as +307.2mm material. The first size class represents the largest particles. The final size class should be zero, as it represents all material that passed through the smallest aperture screen.

- All subsequent columns describe assays of the material.

The following is an example of a material text file:

Compound	FeedA	MillCharge
307.2E-3	0.20	0.02
108.6E-3	0.18	0.06
38.4E-3	0.17	0.04
13.6E-3	0.07	0.03
4.8E-3	0.13	0.03
1.7E-3	0.07	0.04
600.0E-6	0.06	0.18
210.0E-6	0.02	0.50
75.0E-6	0.10	0.10
0.0E0	0.00	0.00

**add\_assay** ( *name*, *assay* )

Add an assay to the material.

#### Parameters

- **name** – The name of the new assay.
- **assay** – A numpy array containing the size class mass fractions for the assay. The sequence of the assay's elements must correspond to the sequence of the material's size classes.

**create\_empty\_assay** ( )

Create an empty array to store an assay. The array's length will be equal to the number of size classes in the material.

**Returns** A floating point array.

**create\_package** ( *assay=None*, *mass=0.0*, *normalise=True* )

Create a MaterialPackage based on the specified parameters.

#### Parameters

- **assay** – The name of the assay based on which the package must be created.
- **mass** – [kg] The mass of the package.
- **normalise** – Indicates whether the assay must be normalised before creating the package.

**Returns** The created MaterialPackage.

**get\_assay\_total** ( *name* )

Calculate the total of the specified assay.

**Parameters** **name** – The name of the assay.

**Returns** The total mass fraction of the specified assay.

**get\_size\_class\_index** ( *size\_class* )

Determine the index of the specified size class.

**Parameters** **size\_class** – The formula and phase of the specified size class, e.g. 'Fe2O3[S1]'.

**Returns** The index of the specified size class.

**class** auxi.modelling.process.materials.psd. **MaterialPackage** ( *material*, *size\_class\_masses*)

Bases: *auxi.core.objects.Object*

A package of a material consisting of multiple particle size classes.

Properties defined here:

#### Parameters

- **material** – A reference to the Material to which self belongs.
- **size\_class\_masses** – [kg] [kg] The masses of the size classes in the package.

**add\_to** ( *other*)

Add another psd material package to this material package.

**Parameters** **other** – The other material package.

**clear** ( )

Set all the size class masses in the package to zero.

**clone** ( )

Create a complete copy of self.

**Returns** A MaterialPackage that is identical to self.

**extract** ( *other*)

Extract 'other' from self, modifying self and returning the extracted material as a new package.

**Parameters** **other** – Can be one of the following:

- float: A mass equal to other is extracted from self. Self is reduced by other and the extracted package is returned as a new package.
- tuple (size class, mass): The other tuple specifies the mass of a size class to be extracted. It is extracted from self and the extracted mass is returned as a new package.
- string: The 'other' string specifies the size class to be extracted. All of the mass of that size class will be removed from self and a new package created with it.

**Returns** A new material package containing the material that was extracted from self.

**get\_assay** ( )

Determine the assay of self.

**Returns** [mass fractions] An array containing the assay of self.

**get\_mass** ( )

Determine the mass of self.

returns: [kg] The mass of self.

**get\_size\_class\_mass** ( *size\_class* )

Determine the mass of the specified size class in self.

**Parameters** **size\_class** – The formula and phase of the size class,  
e.g. 'Fe2O3[S1]'

**Returns** [kg] The mass of the size class in self.

**get\_size\_class\_mass\_fraction** ( *size\_class* )

Determine the mass fraction of the specified size class in self.

**Parameters** **size\_class** – The formula and phase of the size class,  
e.g. 'Fe2O3[S1]'

**Returns** The mass fraction of the size class in self.

## auxi.modelling.process.materials.psd\_test module

This module provides testing code for the psdmaterial module.

@author: Ex Mente Technologies (Pty) Ltd

**class** auxi.modelling.process.materials.psd\_test. **PsdMaterialPackageUnitTests**

Bases: unittest.case.TestCase

Tester for the auxi.modelling.process.materials.psd.material.MaterialPackage class.

**setUp** ( )

**test\_add\_operator\_1** ( )

other = MaterialPackage Test whether the add operator calculates the resulting package correctly.

**test\_add\_operator\_3** ( )

other = tuple (size\_class, mass) Test whether the add operator calculates the resulting package correctly. Results were checked against FactSage results. They are not exactly the same, since the magnetic and other non-cp contributions are omitted by the thermo module.

**test\_clone** ( )

**test\_constructor** ( )

**test\_extract\_1** ( )

**test\_get\_assay** ( )

**test\_get\_mass** ( )

**test\_get\_size\_class\_mass** ( )

**test\_multiply\_operator** ( )

```

    test_subtract_operator_2 ( )
    test_subtract_operator_3 ( )
class auxi.modelling.process.materials.psd_test.PsdMaterialUnitTester ( method
    Bases: unittest.case.TestCase
    Tester for the auxi.modelling.process.materials.psd.Material class.
    setUp ( )
    test_add_assay ( )
    test_constructor ( )
    test_create_empty_assay ( )
    test_create_package ( )
    test_get_assay_total ( )
    test_get_size_class_index ( )

```

## auxi.modelling.process.materials.slurry module

This module provides material and material package classes that can do size distribution and slurry calculations.

```

class auxi.modelling.process.materials.slurry.Material ( name,
                                                         file_path,
                                                         de-
                                                         scrip-
                                                         tion=None)

```

Bases: *auxi.core.objects.NamedObject*

Represents a particulate material consisting of multiple particle size classes.

### Parameters

- **name** – The material’s name.
- **file\_path** – The path of the material definition file.
- **description** – the material’s description

The format of the text file is as follows:

- The lines are space separated. The values in a line are separated by one or more spaces.
- The first line is a heading line.
- The second line contains the density of the solid material.
- The third line contains the water fraction of the slurry (wet basis).
- All subsequent lines contain a particle size, followed by mass fractions (dry basis).
- Particle sizes are indicated in [meter].

- The first column lists the particle sizes in the material. Each class must be interpreted as “mass fraction retained”. In other words if the size class is indicated as 307.2E-3, it means that it is the class of material retained on a 307.2mm screen, and can also be thought of as +307.2mm material. The first size class represents the largest particles. The final size class should be zero, as it represents all material that passed through the smallest aperture screen.
- All subsequent columns describe assays of the material.

The following is an example of a material text file:

SizeClass	DryFeedA	DryMillCharge	WetFeedA	WetMillCharge	Water
solid_density	3.00	3.00	3.00	3.00	
1.0.					
H2O	0.00	0.00	0.80	0.60	
1.00					
307.2E-3	0.20	0.02	0.20	0.02	
0.00					
108.6E-3	0.18	0.06	0.18	0.06	
0.00					
38.4E-3	0.17	0.04	0.17	0.04	
0.00					
13.6E-3	0.07	0.03	0.07	0.03	
0.00					
4.8E-3	0.13	0.03	0.13	0.03	
0.00					
1.7E-3	0.07	0.04	0.07	0.04	
0.00					
600.0E-6	0.06	0.18	0.06	0.18	
0.00					
210.0E-6	0.02	0.50	0.02	0.50	
0.00					
75.0E-6	0.10	0.09	0.10	0.09	
0.00					
0.0E0	0.00	0.00	0.00	0.00	
0.00					

**add\_assay** ( *name*, *solid\_density*, *H2O\_fraction*, *assay* )

Add an assay to the material.

#### Parameters

- **name** – The name of the new assay.
- **assay** – A numpy array containing the size class mass fractions for the assay. The sequence of the assay’s elements must correspond to the sequence of the material’s size classes.

**create\_empty\_assay** ( )

Create an empty array to store an assay. The array’s length will be equal to the number of size classes in the material.



**Returns** A floating point array.

**create\_package** ( *assay=None, mass=0.0, normalise=True* )

Create a MaterialPackage based on the specified parameters.

**Parameters**

- **assay** – The name of the assay based on which the package must be created.
- **mass** – [kg] The mass of the package.
- **normalise** – Indicates whether the assay must be normalised before creating the package.

**Returns** The created MaterialPackage.

**get\_assay\_total** ( *name* )

Calculate the total of the specified assay.

**Parameters** **name** – The name of the assay.

**Returns** The total mass fraction of the specified assay.

**get\_size\_class\_index** ( *size\_class* )

Determine the index of the specified size class.

**Parameters** **size\_class** – The formula and phase of the specified size class, e.g. 'Fe2O3[S1]'.

**Returns** The index of the specified size class.

**class** `auxi.modelling.process.materials.slurry.MaterialPackage` ( *material, solid\_density, H2O\_mass, size\_class\_masses* )

Bases: `auxi.core.objects.Object`

A package of a slurry material consisting of multiple particle size classes.

**Parameters**

- **material** – A reference to the Material to which self belongs.
- **size\_class\_masses** – [kg] [kg] The masses of the size classes in the package.

**clear** ( )

Set all the size class masses and H2O\_mass in the package to zero and the solid\_density to 1.0

**clone** ( )

Create a complete copy of self.

**Returns** A MaterialPackage that is identical to self.

**extract** ( *other* )

Extract 'other' from self, modifying self and returning the extracted material as a new package.

**Parameters other** – Can be one of the following:

- float: A mass equal to other is extracted from self. Self is reduced by other and the extracted package is returned as a new package.
- tuple (size class, mass): The other tuple specifies the mass of a size class to be extracted. It is extracted from self and the extracted mass is returned as a new package.
- string: The ‘other’ string specifies the size class to be extracted. All of the mass of that size class will be removed from self and a new package created with it.

**Returns** A new material package containing the material that was extracted from self.

**get\_assay ( )**

Determine the assay of self.

**Returns** [mass fractions] An array containing the assay of self.

**get\_density ( )**

Determine the density of self.

**get\_mass ( )**

Determine the mass of self.

**Returns** [kg] The mass of self.

**get\_mass\_fraction\_solids ( )**

Determine the mass fraction of the solids of self.

**get\_size\_class\_mass ( size\_class )**

Determine the mass of the specified size class in self.

**Parameters size\_class** – The formula and phase of the size class, e.g. ‘Fe<sub>2</sub>O<sub>3</sub>[S1]’

**Returns** [kg] The mass of the size class in self.

**get\_size\_class\_mass\_fraction ( size\_class )**

Determine the mass fraction of the specified size class in self.

**Parameters size\_class** – The formula and phase of the size class, e.g. Fe<sub>2</sub>O<sub>3</sub>[S1]

**Returns** The mass fraction of the size class in self.

**get\_solid\_mass ( )**

Determine the solid mass of self.

**Returns** [kg] The solid mass of self.

**get\_volume ( )**

Determine the volume of self.

**get\_volume\_fraction\_solids ( )**

Determine the volume fraction of the solids of self.

## auxi.modelling.process.materials.slurry\_test module

This module provides testing code for the psdslurrymaterial module.

@author: Ex Mente Technologies (Pty) Ltd

```
class auxi.modelling.process.materials.slurry_test. SlurryMaterialPackageUnit
```

```
    Bases: unittest.case.TestCase
```

```
    setUp ( )
```

```
    test___str___ ( )
```

```
    test_add_operator_1 ( )
```

```
        other = MaterialPackage Test whether the add operator calculates the resulting package correctly.
```

```
    test_add_operator_3 ( )
```

```
        other = tuple (size_class, mass) Test whether the add operator calculates the resulting package correctly. Results were checked against FactSage results. They are not exactly the same, since the magnetic and other non-cp contributions are omitted by the thermo module.
```

```
    test_clone ( )
```

```
    test_constructor ( )
```

```
    test_extract_1 ( )
```

```
    test_get_assay ( )
```

```
    test_get_mass ( )
```

```
    test_get_size_class_mass ( )
```

```
    test_multiply_operator ( )
```

```
    test_subtract_operator_2 ( )
```

```
    test_subtract_operator_3 ( )
```

```
class auxi.modelling.process.materials.slurry_test. SlurryMaterialUnitTester
```

```
    Bases: unittest.case.TestCase
```

```
    Tester for the auxi.modelling.process.materials.slurry.Material class.
```

```
    setUp ( )
```

```
    test_add_assay ( )
```

```
    test_constructor ( )
```

```
    test_create_empty_assay ( )
```

```
    test_create_package ( )
```

```
    test_get_assay_total ( )
```

```
    test_get_size_class_index ( )
```

## auxi.modelling.process.materials.thermo module

This module provides a material class that can do thermochemical calculations.

```
class auxi.modelling.process.materials.thermo. Material ( name,  
                                                         file_path,  
                                                         de-  
                                                         scrip-  
                                                         tion=None)
```

Bases: *auxi.core.objects.NamedObject*

Represents a material consisting of multiple chemical compounds, having the ability to do thermochemical calculations.

### Parameters

- **name** – A name for the material.
- **file\_path** – The location of the file containing the material’s data.
- **description** – the material’s description

The format of the text file is as follows:

- The items in a line are separated by one or more spaces or tabs.
- The first line is a heading line. It contains the word “Compound” followed by zero or more assay names.
- Subsequent lines contain a compound formula and phase, followed by a mass fraction for each assay.
- The list of compounds and mass fractions can be ended off with a “#” character. This indicates that custom material properties follow below in the lines below the hash.
- If a custom material property is defined, a value must be provided for each assay name. A price custom property is used as an example below.

The following is an example of a material text file:

Compound	IlmeniteA	IlmeniteB	IlmeniteC
Al2O3[S1]	0.01160	0.01550	0.00941
CaO[S]	0.00022	0.00001	0.00017
Cr2O3[S]	0.00008	0.00022	0.00011
Fe2O3[S1]	0.20200	0.47300	0.49674
Fe3O4[S1]	0.00000	0.00000	0.00000
FeO[S1]	0.27900	0.19100	0.00000
K2O[S]	0.00004	0.00001	0.00005
MgO[S]	0.01040	0.00580	0.01090
MnO[S]	0.00540	0.00480	0.00525
Na2O[S1]	0.00007	0.00005	0.00031
P4O10[S]	0.00001	0.00032	0.00015
SiO2[S1]	0.00850	0.00490	0.01744
TiO2[S1]	0.47700	0.29400	0.45949

V2O5[S]	0.00360	0.00800	0.00000
#			
Price[USD/kg]	1.2	1.3	1.1

**add\_assay** ( *name*, *assay* )

Add an assay to the material.

#### Parameters

- **name** – Assay name.
- **assay** – Numpy array containing the compound mass fractions for the assay. The sequence of the assay's elements must correspond to the sequence of the material's compounds.

**compound\_count** = None

The number of chemical compounds in the material.

**compounds** = None

The material's list of chemical compounds.

**converted\_assays** = None

A dictionary containing converted assays for this material.

**create\_empty\_assay** ( )

Create an empty array to store an assay.

The array's length will be equal to the number of compounds in the material.

**Returns** Empty assay array.

**create\_package** ( *assay=None*, *mass=0.0*, *P=1.0*, *T=25.0*, *normalise=True* )

Create a MaterialPackage based on the specified parameters.

#### Parameters

- **assay** – Name of the assay to be used to create the package.
- **mass** – Package mass. [kg]
- **P** – Package pressure. [atm]
- **T** – Package temperature. [°C]
- **normalise** – Indicates whether the assay must be normalised before creating the package.

**Returns** MaterialPackage object.

**description** = None

The material's description.

**get\_assay\_total** ( *name* )

Calculate the total/sum of the specified assay's mass fractions.

**Parameters** **name** – Assay name.

**Returns** Total mass fraction.

**get\_compound\_index** ( *compound* )

Determine the specified compound's index.

**Parameters** **compound** – Formula and phase of a compound, e.g.  
“Fe2O3[S1]”.

**Returns** Compound index.

**name** = None

The material's name.

**raw\_assays** = None

A dictionary containing raw assays for this material.

**class** auxi.modelling.process.materials.thermo. **MaterialPackage** ( *material*,  
*com-*  
*pound\_masses*,  
*P=1.0*,  
*T=25.0*)

Bases: *auxi.core.objects.Object*

Represents a quantity of material consisting of multiple chemical compounds, having a specific mass, pressure, temperature and enthalpy.

#### Parameters

- **material** – A reference to the Material to which self belongs.
- **compound\_masses** – Package compound masses. [kg]
- **P** – Package pressure. [atm]
- **T** – Package temperature. [°C]

**H**

Get the enthalpy of the package.

**Returns** Enthalpy. [kWh]

**P**

Determine the pressure of the package.

**Returns** Pressure. [atm]

**T**

Get the temperature of of the package.

**Returns** Temperature. [°C]

**amount**

Determine the sum of mole amounts of all the compounds.

**Returns** Amount. [kmol]

**clear** ( )

Set all the compound masses in the package to zero. Set the pressure to 1, the temperature to 25 and the enthalpy to zero.

**clone** ( )

Create a complete copy of the package.

**Returns** A new MaterialPackage object.

**extract** ( *other* )

Extract 'other' from this package, modifying this package and returning the extracted material as a new package.

**Parameters** **other** – Can be one of the following:

- float: A mass equal to other is extracted from self. Self is reduced by other and the extracted package is returned as a new package.
- tuple (compound, mass): The other tuple specifies the mass of a compound to be extracted. It is extracted from self and the extracted mass is returned as a new package.
- string: The 'other' string specifies the compound to be extracted. All of the mass of that compound will be removed from self and a new package created with it.
- Material: The 'other' material specifies the list of compounds to extract.

**Returns** New MaterialPackage object.

**get\_assay** ( )

Determine the assay of the package.

**Returns** Array of mass fractions.

**get\_compound\_amount** ( *compound* )

Determine the mole amount of the specified compound.

**Returns** Amount. [kmol]

**get\_compound\_amounts** ( )

Determine the mole amounts of all the compounds.

**Returns** List of amounts. [kmol]

**get\_compound\_mass** ( *compound* )

Determine the mass of the specified compound in the package.

**Parameters** **compound** – Formula and phase of a compound, e.g. "Fe<sub>2</sub>O<sub>3</sub>[S1]".

**Returns** Mass. [kg]

**get\_element\_mass** ( *element* )

Determine the mass of the specified elements in the package.

**Returns** Masses. [kg]

**get\_element\_mass\_dictionary** ( )

Determine the masses of elements in the package and return as a dictionary.

**Returns** Dictionary of element symbols and masses. [kg]

**get\_element\_masses** ( *elements=None* )

Determine the masses of elements in the package.

**Returns** Array of element masses. [kg]

**mass**

Get the mass of the package.

**Returns** [kg]

## auxi.modelling.process.materials.thermo\_test module

This module provides testing code for classes in the thermo module.

**class** auxi.modelling.process.materials.thermo\_test. **ThermoMaterialPackageUni**

Bases: unittest.case.TestCase

Unit tester for the auxi.modelling.process.materials.thermo.MaterialPackage class.

**add\_incompatible\_packages** ( )

**setUp** ( )

**test\_\_str\_\_** ( )

**test\_add\_operator\_1** ( )

Test whether the add operator calculates the resulting package correctly. Results were checked against FactSage results. They are not exactly the same, since the magnetic and other non-cp contributions are omitted by the thermo module.

**test\_add\_operator\_2** ( )

**test\_add\_operator\_3** ( )

other = tuple (compound, mass)

Test whether the add operator calculates the resulting package correctly. Results were checked against FactSage results. They are not exactly the same, since the magnetic and other non-cp contributions are omitted by the thermo module.

**test\_add\_operator\_4** ( )

other = tuple (compound, mass, temperature)

Test whether the add operator calculates the resulting package correctly. Results were checked against FactSage results. They are not exactly the same, since the magnetic and other non-cp contributions are omitted by the thermo module.

**test\_clone** ( )

**test\_constructor** ( )

**test\_extract\_1** ( )

**test\_extract\_2** ( )

**test\_extract\_3** ( )



```
test_get_H ( )
test_get_P ( )
test_get_T ( )
test_get_assay ( )
test_get_compound_mass ( )
test_get_element_masses ( )
test_mass ( )
test_multiply_operator ( )
test_set_H ( )
test_set_T ( )
```

```
class auxi.modelling.process.materials.thermo_test. ThermoMaterialUnitTester
```

```
    Bases: unittest.case.TestCase
```

Unit tester for the auxi.modelling.process.materials.thermo.Material class.

```
setUp ( )
test_add_assay ( )
test_constructor ( )
test_create_empty_assay ( )
test_create_package ( )
test_get_assay_total ( )
test_get_compound_index ( )
```

## Module contents

This package provides classes and functions for working with different types of materials and material packages.

## Module contents

The purpose of this package is to provide common classes and functions for the the auxi.modelling.process namespace

## Module contents

The purpose of this package is to provide common classes and functions for the auxi.modelling namespace

## auxi.tools package

### Subpackages

## auxi.tools.chemistry package

### Submodules

## auxi.tools.chemistry.stoichiometry module

This module provides a number of functions for doing stoichiometry calculations.

```
class auxi.tools.chemistry.stoichiometry. Element ( period, group,  
                                                    atomic_number,  
                                                    symbol, molar_mass)
```

Bases: *auxi.core.objects.Object*

An element in the periodic table.

#### Parameters

- **period** – Period to which the element belongs.
- **group** – Group to which the element belongs.
- **atomic\_number** – Number of protons in the element's nucleus.
- **symbol** – Element's symbol.
- **molar\_mass** – [kg/kmol] Element's standard atomic mass.

```
auxi.tools.chemistry.stoichiometry. amount ( compound, mass)
```

Calculate the number of moles in the specified mass of a chemical compound.

#### Parameters

- **compound** – Formula and phase of a compound, e.g. 'Fe2O3[S1]'. The phase may be omitted.
- **mass** – [kg]

**Returns** Amount. [kmol]

```
auxi.tools.chemistry.stoichiometry. amount_fractions ( masses)
```

Calculate the mole fractions from the specified compound masses.

**Parameters** **masses** – [kg] dictionary, e.g. {'SiO2': 3.0, 'FeO', 1.5}

**Returns** [kg] dictionary

```
auxi.tools.chemistry.stoichiometry. amounts ( masses)
```

Calculate the amounts from the specified compound masses.

**Parameters** **masses** – [kg] dictionary, e.g. {'SiO2': 3.0, 'FeO', 1.5}

**Returns** [kmol] dictionary

```
auxi.tools.chemistry.stoichiometry.convert_compound ( mass,  
                                                         source,  
                                                         target,  
                                                         ele-  
                                                         ment)
```

Convert the specified mass of the source compound to the target using element as basis.

**Parameters**

- **mass** – Mass of from\_compound. [kg]
- **source** – Formula and phase of the original compound, e.g. 'Fe2O3[S1]'.  
• **target** – Formula and phase of the target compound, e.g. 'Fe[S1]'.  
• **element** – Element to use as basis for the conversion, e.g. 'Fe' or 'O'.

**Returns** Mass of target. [kg]

```
auxi.tools.chemistry.stoichiometry.element_mass_fraction ( compound,  
                                                            el-  
                                                            e-  
                                                            ment)
```

Determine the mass fraction of an element in a chemical compound.

**Parameters**

- **compound** – Formula of the chemical compound, 'FeCr2O4'.  
• **element** – Element, e.g. 'Cr'.

**Returns** Element mass fraction.

```
auxi.tools.chemistry.stoichiometry.element_mass_fractions ( compound,  
                                                            el-  
                                                            e-  
                                                            ments)
```

Determine the mass fractions of a list of elements in a chemical compound.

**Parameters**

- **compound** – Formula and phase of a chemical compound, e.g. 'Fe2O3[S1]'.  
• **elements** – List of elements, ['Si', 'O', 'Fe'].

**Returns** Mass fractions.

```
auxi.tools.chemistry.stoichiometry.elements ( compounds)
```

Determine the set of elements present in a list of chemical compounds.

The list of elements is sorted alphabetically.

**Parameters** **compounds** – List of compound formulas and phases, e.g. ['Fe2O3[S1]', 'Al2O3[S1]'].

**Returns** List of elements.

`auxi.tools.chemistry.stoichiometry.mass (compound, amount)`

Calculate the mass of the specified amount of a chemical compound.

**Parameters**

- **compound** – Formula and phase of a compound, e.g. 'Fe2O3[S1]'.  
The phase may be omitted.
- **amount** – [kmol]

**Returns** Mass. [kg]

`auxi.tools.chemistry.stoichiometry.mass_fractions (amounts)`

Calculate the mole fractions from the specified compound masses.

**Parameters** **masses** – [kg] dictionary, e.g. {'SiO2': 3.0, 'FeO', 1.5}

**Returns** [kg] dictionary

`auxi.tools.chemistry.stoichiometry.masses (amounts)`

Calculate the masses from the specified compound amounts.

**Parameters** **masses** – [kmol] dictionary, e.g. {'SiO2': 3.0, 'FeO', 1.5}

**Returns** [kg] dictionary

`auxi.tools.chemistry.stoichiometry.molar_mass (compound='')`

Determine the molar mass of a chemical compound.

The molar mass is usually the mass of one mole of the substance, but here it is the mass of 1000 moles, since the mass unit used in pmpy is kg.

**Parameters** **compound** – Formula of a chemical compound, e.g. 'Fe2O3'.

**Returns** Molar mass. [kg/kmol]

`auxi.tools.chemistry.stoichiometry.stoichiometry_coefficient (compound, element)`

Determine the stoichiometry coefficient of an element in a chemical compound.

**Parameters**

- **compound** – Formula of a chemical compound, e.g. 'SiO2'.
- **element** – Element, e.g. 'Si'.

**Returns** Stoichiometry coefficient.

`auxi.tools.chemistry.stoichiometry.stoichiometry_coefficients (compound, elements)`

Determine the stoichiometry coefficients of the specified elements in the specified chemical compound.

**Parameters**

- **compound** – Formula of a chemical compound, e.g. 'SiO2'.
- **elements** – List of elements, e.g. ['Si', 'O', 'C'].

**Returns** List of stoichiometry coefficients.

## auxi.tools.chemistry.stoichiometry\_test module

This module contains all the code used to test the testee module.

**class** `auxi.tools.chemistry.stoichiometry_test.StoichFunctionTester` ( *methodNa*  
Bases: `unittest.case.TestCase`

The function tester for the stoichiometry module.

**assertAlmostEqual** ( *first, second, places=14, msg=None, delta=None* )

**test\_amount** ( )

Test whether the amount of a compound is calculated correctly.

**test\_convert\_compound** ( )

Test whether compound conversions are calculated correctly.

**test\_element\_mass\_fraction** ( )

Test whether an element mass fraction is calculated correctly.

**test\_element\_mass\_fractions** ( )

Test whether a list of element mass fraction is calculated correctly.

**test\_elements** ( )

Test whether the set of elements in a list of compounds is calculated correctly.

**test\_invalid\_characters** ( )

Test whether an exception is raised when a compound formula contains an invalid character.

**test\_mass** ( )

Test whether the mass of a compound is calculated correctly.

**test\_molar\_mass** ( )

Test whether the molar mass of a compound is calculated correctly.

**test\_stoichiometry\_coefficient** ( )

Test whether the stoichiometry coefficient of a specified element in a compound is calculated correctly.

**test\_stoichiometry\_coefficients** ( )

Test whether the stoichiometry coefficients of a specified list of elements in a compound is calculated correctly.

## auxi.tools.chemistry thermochemistry module

This module provides classes and functions for doing thermochemical calculations.

**class** `auxi.tools.chemistry.thermochemistry.Compound` ( *dictionary* )

Bases: `auxi.core.objects.Object`

Represents a chemical compound.

**Parameters dictionary** – Dictionary containing the data required to initialise the compound.

**Cp** ( *phase, temperature* )

Calculate the heat capacity of a phase of the compound at a specified temperature.

**Parameters**

- **phase** – A phase of the compound, e.g. ‘S’, ‘L’, ‘G’.
- **temperature** – [K]

**Returns** [J/mol/K] Heat capacity.

**G** ( *phase, temperature* )

Calculate the Gibbs free energy of a phase of the compound at a specified temperature.

**Parameters**

- **phase** – A phase of the compound, e.g. ‘S’, ‘L’, ‘G’.
- **temperature** – [K]

**Returns** [J/mol] Gibbs free energy.

**H** ( *phase, temperature* )

Calculate the enthalpy of a phase of the compound at a specified temperature.

**Parameters**

- **phase** – A phase of the compound, e.g. ‘S’, ‘L’, ‘G’.
- **temperature** – [K]

**Returns** [J/mol] Enthalpy.

**S** ( *phase, temperature* )

Calculate the enthalpy of a phase of the compound at a specified temperature.

**Parameters**

- **phase** – A phase of the compound, e.g. ‘S’, ‘L’, ‘G’.
- **temperature** – [K]

**Returns** [J/mol/K] Entropy.

**formula** = None

Chemical formula, e.g. ‘Fe’, ‘CO2’.

**get\_phase\_list** ( )

Get a list of the compound’s phases.

**Returns** List of phases.

**get\_reference** ( )

**molar\_mass** = None

Molar mass. [kg/mol]

`auxi.tools.chemistry.thermochemistry.Cp ( compound_string, temperature, mass=1.0)`

Calculate the heat capacity of the compound for the specified temperature and mass.

#### Parameters

- **compound\_string** – Formula and phase of chemical compound, e.g. 'Fe2O3[S1]'.
- **temperature** – [°C]
- **mass** – [kg]

**Returns** [kWh/K] Heat capacity.

**class** `auxi.tools.chemistry.thermochemistry.CpRecord ( dictionary)`

Bases: `auxi.core.objects.Object`

A heat capacity (Cp) equation record for a compound phase over a specific temperature range.

**Parameters dictionary** – A dictionary containing the data required to initialise the phase.

**Cp** ( temperature)

Calculate the heat capacity of the compound phase.

**Parameters temperature** – [K]

**Returns** [J/mol/K] Heat capacity.

**H** ( temperature)

Calculate the portion of enthalpy of the compound phase covered by this Cp record.

**Parameters temperature** – [K]

**Returns** [J/mol] Enthalpy.

**S** ( temperature)

Calculate the portion of entropy of the compound phase covered by this Cp record.

**Parameters temperature** – [K]

**Returns** Entropy. [J/mol/K]

**Tmax** = None

[K] The maximum temperature of the range covered by this record.

**Tmin** = None

[K] The minimum temperature of the range covered by this record.

`auxi.tools.chemistry.thermochemistry.G ( compound_string, temperature, mass=1.0)`

Calculate the Gibbs free energy of the compound for the specified temperature and mass.

**Parameters**

- **compound\_string** – Formula and phase of chemical compound, e.g. 'Fe2O3[S1]'.
- **temperature** – [°C]
- **mass** – [kg]

**Returns** [kWh] Gibbs free energy.

`auxi.tools.chemistry.thermochemistry.H ( compound_string, temperature, mass=1.0)`

Calculate the enthalpy of the compound for the specified temperature and mass.

**Parameters**

- **compound\_string** – Formula and phase of chemical compound, e.g. 'Fe2O3[S1]'.
- **temperature** – [°C]
- **mass** – [kg]

**Returns** [kWh] Enthalpy.

`class auxi.tools.chemistry.thermochemistry.Phase ( dictionary)`

Bases: `auxi.core.objects.NamedObject`

A phase of a chemical compound.

**Parameters dictionary** – Dictionary containing the data required to initialise the phase.

**Cp** ( *temperature* )

Calculate the heat capacity of the compound phase at the specified temperature.

**Parameters temperature** – [K]

**Returns** [J/mol/K] The heat capacity of the compound phase.

**DHref = None**

[J/mol] The formation enthalpy of the phase at Tref.

**G** ( *temperature* )

Calculate the heat capacity of the compound phase at the specified temperature.

**Parameters temperature** – [K]

**Returns** [J/mol] The Gibbs free energy of the compound phase.

**H** ( *temperature* )

Calculate the enthalpy of the compound phase at the specified temperature.

**Parameters temperature** – [K]

**Returns** [J/mol] The enthalpy of the compound phase.

**S** ( *temperature* )

Calculate the entropy of the compound phase at the specified temperature.



**Parameters** **temperature** – [K]

**Returns** [J/mol/K] The entropy of the compound phase.

**Sref = None**

[J/mol/K] The standard entropy of the phase at Tref.

**Tref = None**

[K] The reference temperature of the phase.

**name = None**

The phase's name, e.g. solid, liquid, gas, etc.

**symbol = None**

The phase's symbol, e.g. S1 = solid 1, L = liquid, etc.

`auxi.tools.chemistry.thermochemistry.S ( compound_string, temperature, mass=1.0)`

Calculate the entropy of the compound for the specified temperature and mass.

**Parameters**

- **compound\_string** – Formula and phase of chemical compound, e.g. 'Fe2O3[S1]'.
- **temperature** – [°C]
- **mass** – [kg]

**Returns** [kJ/mol/K] Entropy.

`auxi.tools.chemistry.thermochemistry.get_datafile_references ( )`  
Retrieve all the references used by the datafiles.

`auxi.tools.chemistry.thermochemistry.list_compounds ( )`  
List all compounds that are currently loaded in the thermo module, and their phases.

`auxi.tools.chemistry.thermochemistry.load_data_auxi ( path='' )`  
Load all the thermochemical data auxi files located at a path.

**Parameters** **path** – Path at which the data files are located.

`auxi.tools.chemistry.thermochemistry.load_data_factsage ( path='' )`  
Load all the thermochemical data factsage files located at a path.

**Parameters** **path** – Path at which the data files are located.

`auxi.tools.chemistry.thermochemistry.molar_mass ( compound)`  
Determine the molar mass of a chemical compound.

**Parameters** **compound** – Formula of a chemical compound, e.g. 'Fe2O3'.

**Returns** [kg/mol] Molar mass.

`auxi.tools.chemistry.thermochemistry.write_compound_to_auxi_file ( directory, compound)`  
Writes a compound to an auxi file at the specified directory.

### Parameters

- **dir** – The directory.
- **compound** – The compound.

## auxi.tools.chemistry.thermochemistry\_test module

This module provides testing code for the thermochemistry module.

**class** `auxi.tools.chemistry.thermochemistry_test.ThermoFunctionTester` (*method*  
Bases: `unittest.case.TestCase`

The function tester for the thermochemistry module.

**assertAlmostEqual** (*first, second, places=14, msg=None, delta=None*)

**test\_Cp** ( )

**test\_G** ( )

**test\_H** ( )

**test\_S** ( )

**test\_compound\_get\_phase\_list** ( )

**test\_cpRecord\_\_str\_\_** ( )

**test\_get\_datafile\_references** ( )

**test\_get\_reference** ( )

**test\_load\_data\_auxi** ( )

**test\_molar\_mass** ( )

**test\_phase\_\_str\_\_** ( )

## Module contents

This package provides chemistry-related tools to make various tasks quick, easy and accurate.

## auxi.tools.materialphysicalproperties package

### Submodules

## auxi.tools.materialphysicalproperties.core module

This module provides tools for calculating material physical properties.

**class** `auxi.tools.materialphysicalproperties.core.DataSet ( csvfilepath)`  
 Bases: `object`

Contains a data set used to create and/or test a material physical property model.

**Parameters** `csvfilepath` – path to the csv file that contains the data

**create\_template** ( `material, path, show=False`)

Create a template csv file for a data set.

#### Parameters

- **material** – the name of the material
- **path** – the path of the directory where the file must be written
- **show** – a boolean indicating whether the created file should be displayed after creation

**class** `auxi.tools.materialphysicalproperties.core.Model ( material,`  
`pro-`  
`prty,`  
`sym-`  
`bol,`  
`dis-`  
`play_symbol,`  
`units,`  
`state_schema,`  
`refer-`  
`ences,`  
`datasets)`

Bases: `auxi.core.objects.Object`

Base class of models that describe the variation of a specific material physical property.

**param material** the name of the material being described, e.g. “Air”

**param proprty** the name of the property being described, e.g. “density”

**param symbol** the symbol of the property being described, e.g. “rho”

**param display symbol** the display symbol of the property being described, e.g. “

ho”

**param units** the units used to express the property, e.g. “kg/m3”

**param references** a list of literature references on which this model implementation is based, e.g. [‘lienhard2015’, ‘smith2006’]

**param datasets** a list of data sets on which this model implementation is based, e.g. ['dataset-air-lienhard2015.csv']

**calculate** ( *\*\*state* )

Base calculate method for models. Validates the material state parameter(s).

**Parameters *\*\*state*** – The material state

**class** `auxi.tools.materialphysicalproperties.core.StateOfMatter`

Bases: `enum.Enum`

**gas** = <StateOfMatter.gas: 4>

**gas\_plasma** = <StateOfMatter.gas\_plasma: 12>

**liquid** = <StateOfMatter.liquid: 2>

**liquid\_gas\_plasma** = <StateOfMatter.liquid\_gas\_plasma: 14>

**liquid\_plasma** = <StateOfMatter.liquid\_plasma: 10>

**plasma** = <StateOfMatter.plasma: 8>

**solid** = <StateOfMatter.solid: 1>

**solid\_gas** = <StateOfMatter.solid\_gas: 5>

**solid\_liquid** = <StateOfMatter.solid\_liquid: 3>

**solid\_liquid\_gas** = <StateOfMatter.solid\_liquid\_gas: 7>

**solid\_liquid\_gas\_plasma** = <StateOfMatter.solid\_liquid\_gas\_plasma: 15>

**solid\_liquid\_plasma** = <StateOfMatter.solid\_liquid\_plasma: 11>

**solid\_plasma** = <StateOfMatter.solid\_plasma: 9>

**unknown** = <StateOfMatter.unknown: 0>

## auxi.tools.materialphysicalproperties.core\_test module

This module contains all the code used to test the testee module.

**class** `auxi.tools.materialphysicalproperties.core_test.DataSetTester` ( *methodN*

Bases: `unittest.case.TestCase`

The tester for the DataSet class.

**test\_construct** ( )

Test whether a data set is constructed successfully from a file.

**test\_create\_template** ( )

**test\_description** ( )

Test whether the data set description is successfully loaded.

**test\_material** ( )

Test whether the material name is successfully loaded.

**test\_name ( )**

Test whether the data set name is successfully loaded.

**test\_parameter\_names ( )**

Test whether the data set parameter names are successfully loaded.

**test\_parameter\_symbols ( )**

Test whether the data set parameter symbols are successfully loaded.

**test\_parameter\_units ( )**

Test whether the data set parameter units are successfully loaded.

**test\_reference ( )**

Test whether the data set reference is successfully loaded.

## **auxi.tools.materialphysicalproperties.gases module**

This module provides physical property data sets and models for gases.

## **auxi.tools.materialphysicalproperties.idealgas module**

This module provides tools for calculating physical properties of an ideal gas.

**class** `auxi.tools.materialphysicalproperties.idealgas.BetaT`

Bases: `auxi.tools.materialphysicalproperties.core.Model`

A model that describes the variation in the thermal expansion coefficient of an ideal gas as a function of temperature.

**calculate ( \*\*state )**

Calculate the thermal expansion coefficient at the specified temperature:

**Parameters** **T** – [K] temperature

**Returns** [1/K] thermal expansion coefficient

The **\*\*state** parameter contains the keyword argument(s) specified above that are used to describe the state of the material.

**class** `auxi.tools.materialphysicalproperties.idealgas.RhoT ( molar_mass, P )`

Bases: `auxi.tools.materialphysicalproperties.core.Model`

A model that describes the variation in density of an ideal gas as a function of temperature.

**Parameters**

- **molar\_mass** – [g/mol] average molar mass of the gas
- **P** – [Pa] pressure

**P = None**

[Pa] pressure

**calculate** ( *\*\*state* )

Calculate the density at the specified temperature.

**Parameters** **T** – [K] temperature

**Returns** [kg/m3] density

The *\*\*state* parameter contains the keyword argument(s) specified above that are used to describe the state of the material.

**mm** = **None**

[kg/mol] average molar mass of the gas

**class** `auxi.tools.materialphysicalproperties.idealgas.RhoTP` ( *molar\_mass* )

Bases: `auxi.tools.materialphysicalproperties.core.Model`

A model that describes the variation in density of an ideal gas as a function of temperature and pressure.

**Parameters** **molar\_mass** – [g/mol] average molar mass of the gas

**calculate** ( *\*\*state* )

Calculate the density at the specified temperature and pressure.

**Parameters**

- **T** – [K] temperature
- **P** – [Pa] pressure

**Returns** [kg/m3] density

The *\*\*state* parameter contains the keyword argument(s) specified above that are used to describe the state of the material.

**mm** = **None**

[kg/mol] average molar mass of the gas

**class** `auxi.tools.materialphysicalproperties.idealgas.RhoTPx`

Bases: `auxi.tools.materialphysicalproperties.core.Model`

A model that describes the variation in density of an ideal gas as a function of temperature, pressure, and molar composition.

**calculate** ( *\*\*state* )

Calculate the density at the specified temperature, pressure, and composition.

**Parameters**

- **T** – [K] temperature
- **P** – [Pa] pressure
- **x** – [mole fraction] dictionary of compounds and mole fractions

**Returns** [kg/m3] density

The *\*\*state* parameter contains the keyword argument(s) specified above that are used to describe the state of the material.

## auxi.tools.materialphysicalproperties.idealgas\_test module

This module contains all the code used to test the testee module.

**class** auxi.tools.materialphysicalproperties.idealgas\_test. **BetaTTester** ( *method*  
Bases: unittest.case.TestCase

The tester for the BetaT class.

**test\_calculate** ( )

Test whether the property value is calculated successfully.

**test\_call** ( )

Test whether the property value is calculated successfully via the `__call__` magic method.

**test\_construct** ( )

Test whether a model is constructed successfully.

**class** auxi.tools.materialphysicalproperties.idealgas\_test. **RhoTPTester** ( *method*  
Bases: unittest.case.TestCase

The tester for the RhoTP class.

**test\_calculate** ( )

Test whether the property value is calculated successfully.

**test\_call** ( )

Test whether the property value is calculated successfully via the `__call__` magic method.

**test\_create** ( )

Test whether a model is created successfully.

**class** auxi.tools.materialphysicalproperties.idealgas\_test. **RhoTPxTester** ( *method*  
Bases: unittest.case.TestCase

The tester for the RhoTPx class.

**test\_calculate** ( )

Test whether the property value is calculated successfully.

**test\_call** ( )

Test whether the property value is calculated successfully via the `__call__` magic method.

**test\_create** ( )

Test whether a model is created successfully.

**class** auxi.tools.materialphysicalproperties.idealgas\_test. **RhoTTester** ( *method*  
Bases: unittest.case.TestCase

The tester for the RhoT class.

**test\_calculate** ( )

Test whether the property value is calculated successfully.

**test\_call ( )**

Test whether the property value is calculated successfully via the `__call__` magic method.

**test\_create ( )**

Test whether a model is created successfully.

## auxi.tools.materialphysicalproperties.liquids module

This module provides physical property data sets and models for liquids.

## auxi.tools.materialphysicalproperties.polynomial module

This module provides tools for calculating material physical properties.

**class** `auxi.tools.materialphysicalproperties.polynomial.PolynomialModelT` ( *ma*  
*pro*  
*pr*  
*syn*  
*bo*  
*dis*  
*pla*  
*un*  
*ref*  
*er-*  
*enc*  
*da*  
*co-*  
*eff*

Bases: `auxi.tools.materialphysicalproperties.core.Model`

A model that uses polynomial fits on experimental data to describe the variation of a specific material physical property as a function of temperature.

**param material** the name of the material being described, e.g. “Air”

**param proprty** the name of the property being described, e.g. “density”

**param symbol** the symbol of the property being described, e.g. “rho”

**param display symbol** the display symbol of the property being described, e.g. “

ho”

**param units** the units used to express the property, e.g. “kg/m3”



**param references** a list of literature references on which this model implementation is based, e.g. ['lienhard2015', 'smith2006']

**param datasets** a list of data sets on which this model implementation is based, e.g. ['dataset-air-lienhard2015.csv']

**param coeffs** polynomial coefficients sorted from highest to lowest power

**calculate** ( *\*\*state* )

Calculate the material physical property at the specified temperature in the units specified by the object's 'property\_units' property.

**Parameters** **T** – [K] temperature

**Returns** physical property value

**create** ( *dataset, symbol, degree* )

Create a model object from the data set for the property specified by the supplied symbol, using the specified polynomial degree.

**Parameters**

- **dataset** – a DataSet object
- **symbol** – the symbol of the property to be described, e.g. 'rho'
- **degree** – the polynomial degree to use

**Returns** a new PolynomialModelT object

**plot** ( *dataset, path, show=False* )

## auxi.tools.materialphysicalproperties.polynomial\_test module

This module contains all the code used to test the testee module.

**class** `auxi.tools.materialphysicalproperties.polynomial_test.PolynomialModel`

Bases: `unittest.case.TestCase`

The tester for the PolynomialModelT class.

**test\_calculate** ( )

Test whether the property value is calculated successfully.

**test\_call** ( )

Test whether the property value is calculated successfully via the `__call__` magic method.

**test\_construct** ( )

Test whether a model is constructed successfully.

**test\_create** ( )

Test whether a model is created successfully from a data set.

**test\_plot ( )**

Test whether the plots are created.

**test\_read ( )**

Test whether a model is created successfully by loading it from a json file.

**test\_write ( )**

Test whether a model is successfully written to a json file.

## auxi.tools.materialphysicalproperties.slags module

This module provides physical property data sets and models for slags.

**class** `auxi.tools.materialphysicalproperties.slags.RiboudViscosityTx`

Bases: `auxi.tools.materialphysicalproperties.core.Model`

A model that describes the variation in the dynamic viscosity of liquid slag as a function of temperature and composition expressed in mole fraction.

**calculate** ( *\*\*state* )

Calculate dynamic viscosity at the specified temperature and composition:

### Parameters

- **T** – [K] temperature
- **x** – [mole fraction] composition dictionary , e.g. {‘SiO2’: 0.25, ‘CaO’: 0.25, ‘MgO’: 0.25, ‘FeO’: 0.25}

**Returns** [Pa.s] dynamic viscosity

The **\*\*state** parameter contains the keyword argument(s) specified above that are used to describe the state of the material.

**class** `auxi.tools.materialphysicalproperties.slags.RiboudViscosityTy`

Bases: `auxi.tools.materialphysicalproperties.slags.RiboudViscosityTx`

A model that describes the variation in the dynamic viscosity of liquid slag as a function of temperature and composition expressed in mass fraction.

**calculate** ( *\*\*state* )

Calculate dynamic viscosity at the specified temperature and composition:

### Parameters

- **T** – [K] temperature
- **y** – [mass fraction] composition dictionary , e.g. {‘SiO2’: 0.25, ‘CaO’: 0.25, ‘MgO’: 0.25, ‘FeO’: 0.25}

**Returns** [Pa.s] dynamic viscosity

The **\*\*state** parameter contains the keyword argument(s) specified above that are used to describe the state of the material.

**class** `auxi.tools.materialphysicalproperties.slags.UrbainViscosityTx`  
Bases: `auxi.tools.materialphysicalproperties.core.Model`

A model that describes the variation in the dynamic viscosity of liquid slag as a function of temperature and composition expressed in mole fraction.

**calculate** ( *\*\*state* )

Calculate dynamic viscosity at the specified temperature and composition:

**Parameters**

- **T** – [K] temperature
- **x** – [mole fraction] composition dictionary , e.g. {‘SiO2’: 0.25, ‘CaO’: 0.25, ‘MgO’: 0.25, ‘FeO’: 0.25}

**Returns** [Pa.s] dynamic viscosity

The **\*\*state** parameter contains the keyword argument(s) specified above that are used to describe the state of the material.

**class** `auxi.tools.materialphysicalproperties.slags.UrbainViscosityTy`  
Bases: `auxi.tools.materialphysicalproperties.slags.UrbainViscosityTx`

A model that describes the variation in the dynamic viscosity of liquid slag as a function of temperature and composition expressed in mass fraction.

**calculate** ( *\*\*state* )

Calculate dynamic viscosity at the specified temperature and composition:

**Parameters**

- **T** – [K] temperature
- **y** – [mass fraction] composition dictionary , e.g. {‘SiO2’: 0.25, ‘CaO’: 0.25, ‘MgO’: 0.25, ‘FeO’: 0.25}

**Returns** [Pa.s] dynamic viscosity

The **\*\*state** parameter contains the keyword argument(s) specified above that are used to describe the state of the material.

## Module contents

This package provides tools to calculate material physical properties.

## auxi.tools.transportphenomena package

### Submodules

#### auxi.tools.transportphenomena.dimensionlessquantities module

This module provides functions to calculate dimensionless quantities used when doing transport phenomena calculations.

```
auxi.tools.transportphenomena.dimensionlessquantities.Gr ( L:  
float,  
Ts:  
float,  
Tf:  
float,  
beta:  
float,  
nu:  
float,  
g:  
float)
```

Calculate the Grashof number.

#### Parameters

- **L** – [m] heat transfer surface characteristic length.
- **Ts** – [K] heat transfer surface temperature.
- **Tf** – [K] bulk fluid temperature.
- **beta** – [1/K] fluid coefficient of thermal expansion.
- **nu** – [m2/s] fluid kinematic viscosity.

**Returns** float

$$\text{Gr} = \frac{g\beta(T_s - T_{inf})L^3}{\nu^2}$$

#### Characteristic dimensions:

- vertical plate: vertical length
- pipe: diameter
- bluff body: diameter

```
auxi.tools.transportphenomena.dimensionlessquantities. Nu ( L:
                                                                    float,
                                                                    h:
                                                                    float,
                                                                    k:
                                                                    float)
                                                                    →
                                                                    float
```

Calculate the Nusselt number.

#### Parameters

- **L** – [m] heat transfer surface characteristic length.
- **h** – [W/K/m<sup>2</sup>] convective heat transfer coefficient.
- **k** – [W/K/m] fluid thermal conductivity.

**Returns** float

```
auxi.tools.transportphenomena.dimensionlessquantities. Pr ( nu:
                                                                    float,
                                                                    al-
                                                                    pha:
                                                                    float)
                                                                    →
                                                                    float
```

Calculate the Prandtl number.

#### Parameters

- **nu** – [m<sup>2</sup>/s] fluid kinematic viscosity / momentum diffusivity.
- **alpha** – [m<sup>2</sup>/s] fluid thermal diffusivity.

**Returns** float

```
auxi.tools.transportphenomena.dimensionlessquantities. Ra ( L:
                                                                    float,
                                                                    Ts:
                                                                    float,
                                                                    Tf:
                                                                    float,
                                                                    al-
                                                                    pha:
                                                                    float,
                                                                    beta:
                                                                    float,
                                                                    nu:
                                                                    float)
                                                                    →
                                                                    float
```

Calculate the Grashof number.

#### Parameters

- **L** – [m] heat transfer surface characteristic length.
- **Ts** – [K] heat transfer surface temperature.
- **Tf** – [K] bulk fluid temperature.
- **alpha** – [m<sup>2</sup>/s] fluid thermal diffusivity.
- **beta** – [1/K] fluid coefficient of thermal expansion.
- **nu** – [m<sup>2</sup>/s] fluid kinematic viscosity.

**Returns** float

$$Ra = Gr * Pr$$

**Characteristic dimensions:**

- vertical plate: vertical length
- pipe: diameter
- bluff body: diameter

```
auxi.tools.transportphenomena.dimensionlessquantities. Re ( L:
                                                         float,
                                                         v:
                                                         float,
                                                         nu:
                                                         float)
                                                         →
                                                         float
```

Calculate the Reynolds number.

**Parameters**

- **L** – [m] surface characteristic length.
- **v** – [m/s] fluid velocity relative to the object.
- **nu** – [m<sup>2</sup>/s] fluid kinematic viscosity.

**Returns** float

```
auxi.tools.transportphenomena.dimensionlessquantities. Sh ( L:
                                                         float,
                                                         h:
                                                         float,
                                                         D:
                                                         float)
                                                         →
                                                         float
```

Calculate the Sherwood number.

**Parameters**

- **L** – [m] mass transfer surface characteristic length.
- **h** – [m/s] mass transfer coefficient.

- $D$  – [m<sup>2</sup>/s] fluid mass diffusivity.

**Returns** float

## Module contents

This package provides tools to do calculations related to heat transfer, mass transfer, and fluid flow.

## Submodules

### auxi.tools.physicalconstants module

This module provides a set of physical constants that are used frequently.

`auxi.tools.physicalconstants.F = 96485.3365`

[C·mol<sup>-1</sup>] Faraday constant

`auxi.tools.physicalconstants.G = 6.67408e-11`

[m<sup>3</sup>.kg<sup>-1</sup>.s<sup>-2</sup>] Newtonian constant of gravitation

`auxi.tools.physicalconstants.N_A = 6.02214129e+23`

[mol<sup>-1</sup>] Avogadro's number

`auxi.tools.physicalconstants.R = 8.3144621`

[J.K<sup>-1</sup>.mol<sup>-1</sup>] gas constant

`auxi.tools.physicalconstants.c = 299792458`

[m.s<sup>-1</sup>] speed of light in vacuum

`auxi.tools.physicalconstants.g = 9.80665`

[m.s<sup>-2</sup>] standard acceleration of gravity

`auxi.tools.physicalconstants.h = 6.62607004e-34`

[J.s] Planck constant

`auxi.tools.physicalconstants.h_bar = 1.0545718e-34`

[J.s] reduced Planck constant ( $\hbar$ )

`auxi.tools.physicalconstants.k_B = 1.3806488e-23`

[J.K<sup>-1</sup>] Boltzmann constant

`auxi.tools.physicalconstants.m_u = 1.660538921e-27`

[kg] atomic mass constant

## Module contents

This package provides tools to make common tasks quick, easy and accurate.

## 4.1.2 Submodules

### auxi.tests module

This module runs all the tests of the auxi package at once.

## 4.1.3 Module contents

A toolkit to help metallurgical process engineers to rapidly do day-to-day calculations.

auxi is a toolkit to help metallurgical process engineers with their day-to-day tasks. Many of the calculations that we do require things like molar masses, conversion of one compound to another using stoichiometry, heat transfer calculations, mass balances, energy balances, etc. It is usually quite time consuming to get started with these calculations in a tool like Excel. auxi aims to save you time by making many of these calculations available from within python.

We hope that auxi will help you spend less time focusing on searching for formulas and data, and setting up calculations, and more on thinking about the problems that you need to solve with these calculations. Enjoy!

If you need more information about how to use auxi, please refer the documentation at <https://auxi.readthedocs.org/en/latest/>.



## INDICES AND TABLES

- genindex
- modindex
- search



## PYTHON MODULE INDEX

### a

[auxi](#), [124](#)  
[auxi.core](#), [61](#)  
[auxi.core.helpers](#), [57](#)  
[auxi.core.helpers\\_test](#), [57](#)  
[auxi.core.objects](#), [58](#)  
[auxi.core.objects\\_test](#), [58](#)  
[auxi.core.reporting](#), [59](#)  
[auxi.core.reporting\\_test](#), [59](#)  
[auxi.core.time](#), [60](#)  
[auxi.core.time\\_test](#), [61](#)  
[auxi.modelling](#), [101](#)  
[auxi.modelling.business](#), [72](#)  
[auxi.modelling.business.basic\\_test](#), [64](#)  
[auxi.modelling.business.models\\_test](#), [66](#)  
[auxi.modelling.business.structure\\_test](#), [70](#)  
[auxi.modelling.financial](#), [80](#)  
[auxi.modelling.financial.des\\_test](#), [77](#)  
[auxi.modelling.financial.reporting\\_test](#), [80](#)  
[auxi.modelling.process](#), [101](#)  
[auxi.modelling.process.materials](#), [101](#)  
[auxi.modelling.process.materials.chem\\_test](#), [84](#)  
[auxi.modelling.process.materials.core](#), [85](#)  
[auxi.modelling.process.materials.core\\_test](#), [87](#)  
[auxi.modelling.process.materials.psd\\_test](#), [90](#)  
[auxi.modelling.process.materials.slurry\\_test](#), [95](#)  
[auxi.modelling.process.materials.thermo\\_test](#), [100](#)  
[auxi.tests](#), [124](#)  
[auxi.tools](#), [123](#)  
[auxi.tools.chemistry](#), [110](#)  
[auxi.tools.chemistry.stoichiometry\\_test](#), [105](#)  
[auxi.tools.chemistry.thermochemistry\\_test](#), [110](#)  
[auxi.tools.materialphysicalproperties](#), [119](#)  
[auxi.tools.materialphysicalproperties.combustion\\_test](#), [110](#)  
[auxi.tools.materialphysicalproperties.composition\\_test](#), [112](#)  
[auxi.tools.materialphysicalproperties.gas\\_test](#), [115](#)  
[auxi.tools.materialphysicalproperties.identification\\_test](#), [116](#)  
[auxi.tools.materialphysicalproperties.identification\\_test](#), [116](#)  
[auxi.tools.materialphysicalproperties.liquid\\_test](#), [117](#)  
[auxi.tools.materialphysicalproperties.polymer\\_test](#), [118](#)  
[auxi.tools.physicalconstants](#), [123](#)  
[auxi.tools.transportphenomena](#), [123](#)  
[auxi.tools.transportphenomena.dimensionless\\_test](#), [120](#)



## A

- AccountType (class in `auxi.modelling.financial.des`), 72
- Activity (class in `auxi.modelling.business.structure`), 67
- ActivityUnitTester (class in `auxi.modelling.business.structure_test`), 70
- `add_activity()` (`auxi.modelling.business.structure.Component` method), 68
- `add_assay()` (`auxi.modelling.process.materials.chem.MaterialPackage` method), 82
- `add_assay()` (`auxi.modelling.process.materials.psd.MaterialPackage` method), 88
- `add_assay()` (`auxi.modelling.process.materials.shurry.MaterialPackage` method), 92
- `add_assay()` (`auxi.modelling.process.materials.thermo.MaterialPackage` method), 97
- `add_incompatible_packages()` (`auxi.modelling.process.materials.chem_test.ChemMaterialPackageUnitTester` method), 84
- `add_incompatible_packages()` (`auxi.modelling.process.materials.thermo_test.ThermoMaterialPackageUnitTester` method), 100
- `add_to()` (`auxi.modelling.process.materials.chem.MaterialPackage` method), 83
- `add_to()` (`auxi.modelling.process.materials.psd.MaterialPackage` method), 89
- `alpha()` (`auxi.modelling.process.materials.core.MaterialPackage` method), 86
- `amount` (`auxi.modelling.business.basic.BasicLoanActivity` attribute), 63
- `amount` (`auxi.modelling.process.materials.thermo.MaterialPackage` attribute), 98
- `amount()` (in module `auxi.tools.chemistry.stoichiometry`), 102
- `amount_fractions()` (in module `auxi.tools.chemistry.stoichiometry`), 102
- `amounts()` (in module `auxi.tools.chemistry.stoichiometry`), 102
- `assertAlmostEqual()` (`auxi.modelling.process.materials.chem_test.ChemMaterialPackageUnitTester` method), 85
- `assertAlmostEqual()` (`auxi.modelling.process.materials.psd.MaterialPackageUnitTester` method), 105
- `assertAlmostEqual()` (`auxi.modelling.process.materials.shurry.MaterialPackageUnitTester` method), 110
- `asset` (`auxi.modelling.financial.des.AccountType` attribute), 72
- AT (in module `auxi.modelling.financial.des`), 72
- `auxi` (module), 124
- `auxi_core` (module), 61
- `auxi.core.helpers` (module), 57
- `auxi.core.helpers_test` (module), 57
- `auxi.core.objects` (module), 58
- `auxi.core.objects_test` (module), 58
- `auxi.core.reporting` (module), 59
- `auxi.core.reporting_test` (module), 59
- `auxi.core.time` (module), 60
- `auxi.core.time_test` (module), 61
- `auxi.modelling` (module), 101
- `auxi.modelling.business` (module), 72
- `auxi.modelling.business.basic` (module), 61
- `auxi.modelling.business.basic_test` (module), 64
- `auxi.modelling.business.models` (module), 65
- `auxi.modelling.business.models_test` (module), 66
- `auxi.modelling.business.structure` (module), 67

- 67
- auxi.modelling.business.structure\_test (module), 70
- auxi.modelling.financial (module), 80
- auxi.modelling.financial.des (module), 72
- auxi.modelling.financial.des\_test (module), 77
- auxi.modelling.financial.reporting (module), 78
- auxi.modelling.financial.reporting\_test (module), 80
- auxi.modelling.process (module), 101
- auxi.modelling.process.materials (module), 101
- auxi.modelling.process.materials.chem (module), 81
- auxi.modelling.process.materials.chem\_test (module), 84
- auxi.modelling.process.materials.core (module), 85
- auxi.modelling.process.materials.core\_test (module), 87
- auxi.modelling.process.materials.psd (module), 87
- auxi.modelling.process.materials.psd\_test (module), 90
- auxi.modelling.process.materials.slurry (module), 91
- auxi.modelling.process.materials.slurry\_test (module), 95
- auxi.modelling.process.materials.thermo (module), 96
- auxi.modelling.process.materials.thermo\_test (module), 100
- auxi.tests (module), 124
- auxi.tools (module), 123
- auxi.tools.chemistry (module), 110
- auxi.tools.chemistry.stoichiometry (module), 102
- auxi.tools.chemistry.stoichiometry\_test (module), 105
- auxi.tools.chemistry.thermochemistry (module), 105
- auxi.tools.chemistry.thermochemistry\_test (module), 110
- auxi.tools.materialphysicalproperties (module), 119
- auxi.tools.materialphysicalproperties.core (module), 110
- auxi.tools.materialphysicalproperties.core\_test (module), 112
- auxi.tools.materialphysicalproperties.gases (module), 113
- auxi.tools.materialphysicalproperties.idealgas (module), 113
- auxi.tools.materialphysicalproperties.idealgas\_test (module), 115
- auxi.tools.materialphysicalproperties.liquids (module), 116
- auxi.tools.materialphysicalproperties.polynomial (module), 116
- auxi.tools.materialphysicalproperties.polynomial\_test (module), 117
- auxi.tools.materialphysicalproperties.slags (module), 118
- auxi.tools.physicalconstants (module), 123
- auxi.tools.transportphenomena (module), 123
- auxi.tools.transportphenomena.dimensionlessquantities (module), 120
- ## B
- balance\_sheet (auxi.modelling.financial.reporting.ReportType attribute), 79
- balance\_sheet() (auxi.modelling.financial.des.GeneralLedger method), 73
- BalanceSheet (class in auxi.modelling.financial.reporting), 78
- BasicActivity (class in auxi.modelling.business.basic), 61
- BasicActivityUnitTester (class in auxi.modelling.business.basic\_test), 64
- BasicLoanActivity (class in auxi.modelling.business.basic), 62
- BasicLoanActivityUnitTester (class in auxi.modelling.business.basic\_test), 64
- beta() (auxi.modelling.process.materials.core.Material method), 86
- BetaT (class in auxi.tools.materialphysicalproperties.idealgas), 113

BetaTTester (class in clone() (auxi.modelling.process.materials.psd.MaterialPackage), 89  
 auxi.tools.materialphysicalproperties.idealgas\_test), 89  
 115 clone() (auxi.modelling.process.materials.slurry.MaterialPackage), 93  
 method), 93  
 clone() (auxi.modelling.process.materials.thermo.MaterialPackage), 98  
 method), 98  
 Component (class in  
 calculate() (auxi.tools.materialphysicalproperties.core.Model), 67  
 method), 112  
 calculate() (auxi.tools.materialphysicalproperties.idealgas\_test), 113  
 auxi.modelling.business.structure\_test),  
 calculate() (auxi.tools.materialphysicalproperties.idealgas\_test), 113  
 RhoT  
 method), 113  
 Compound (class in  
 calculate() (auxi.tools.materialphysicalproperties.idealgas\_test), 105  
 method), 114  
 compound\_count  
 calculate() (auxi.tools.materialphysicalproperties.idealgas\_test), 114  
 (auxi.modelling.process.materials.thermo.MaterialPackage), 97  
 calculate() (auxi.tools.materialphysicalproperties.polynomial.PolynomialModelT  
 method), 117  
 compounds (auxi.modelling.process.materials.thermo.MaterialPackage), 97  
 calculate() (auxi.tools.materialphysicalproperties.slags.RhoViscosityTx  
 method), 118  
 convert\_compound() (in module  
 calculate() (auxi.tools.materialphysicalproperties.slags.RhoViscosityTx), 103  
 method), 118  
 calculate() (auxi.tools.materialphysicalproperties.slags.RhoViscosityTx  
 method), 119  
 (auxi.modelling.process.materials.thermo.MaterialPackage), 97  
 calculate() (auxi.tools.materialphysicalproperties.slags.UrhoViscosityTx  
 method), 119  
 Cp() (auxi.modelling.process.materials.core.MaterialPackage), 86  
 cash\_flow (auxi.modelling.financial.reporting.ReportType), 79  
 attribute), 79  
 Cp() (auxi.tools.chemistry.thermochemistry.Compound), 106  
 ChemMaterialPackageUnitTester (class in method), 107  
 auxi.modelling.process.materials.chem\_test), 107  
 84  
 ChemMaterialUnitTester (class in Cp() (auxi.tools.chemistry.thermochemistry.Phase  
 auxi.modelling.process.materials.chem\_test), method), 108  
 85  
 Cp() (in module  
 clear() (auxi.modelling.process.materials.chem.MaterialPackage), 107  
 method), 83  
 clear() (auxi.modelling.process.materials.psd.MaterialPackage), 89  
 method), 89  
 auxi.tools.chemistry.thermochemistry),  
 clear() (auxi.modelling.process.materials.slurry.MaterialPackage), 93  
 method), 93  
 create() (auxi.tools.materialphysicalproperties.polynomial.PolynomialModelT), 117  
 clear() (auxi.modelling.process.materials.thermo.MaterialPackage), 98  
 method), 98  
 create\_account()  
 Clock (class in auxi.core.time), 60  
 (auxi.modelling.financial.des.GeneralLedgerAccount), 74  
 method), 74  
 ClockUnitTester (class in auxi.core.time\_test), 61  
 create\_component()  
 clone() (auxi.modelling.process.materials.chem.MaterialPackage), 83  
 (auxi.modelling.business.structure.Component), 68  
 method), 68

create\_component() (auxi.modelling.business.structure.EntityDhref (auxi.tools.chemistry.thermochemistry.Phase attribute), 97 method), 69 attribute), 108

create\_empty\_assay() (auxi.modelling.process.materials.chem.Material Element (class in auxi.tools.chemistry.stoichiometry), method), 82

create\_empty\_assay() (auxi.modelling.process.materials.psd.Material 102 element\_mass\_fraction() (in module auxi.tools.chemistry.stoichiometry), method), 88

create\_empty\_assay() (auxi.modelling.process.materials.slurry.Material 103 element\_mass\_fractions() (in module auxi.tools.chemistry.stoichiometry), method), 92

create\_empty\_assay() (auxi.modelling.process.materials.thermo.Material 103 elements() (in module auxi.tools.chemistry.stoichiometry), method), 97

create\_entity() (auxi.modelling.business.models.TimeBasedModel 103 Entity (class in auxi.modelling.business.structure), method), 65

create\_package() (auxi.modelling.process.materials.chem.Material 69 EntityUnitTester (class in auxi.modelling.business.structure\_test), method), 82

create\_package() (auxi.modelling.process.materials.psd.Material 71 equity (auxi.modelling.financial.des.AccountType attribute), 72

create\_package() (auxi.modelling.process.materials.slurry.Material 72 expense (auxi.modelling.financial.des.AccountType attribute), 72 method), 93

create\_package() (auxi.modelling.process.materials.thermo.Material 83 extract() (auxi.modelling.process.materials.chem.MaterialPack method), 83

create\_template() (auxi.modelling.process.materials.psd.MaterialPack extract() (auxi.modelling.process.materials.psd.MaterialPack method), 89

create\_template() (auxi.tools.materialphysicalproperties.core.DataSet extract() (auxi.modelling.process.materials.slurry.MaterialPack method), 93 method), 111

create\_transaction() (auxi.modelling.process.materials.thermo.MaterialPack extract() (auxi.modelling.process.materials.thermo.MaterialPack method), 99 method), 73

csv (auxi.core.reporting.ReportFormat attribute), 59

## D

DataSet (class in auxi.tools.materialphysicalproperties.core.DataSet, 110

DataSetTester (class in auxi.tools.materialphysicalproperties.core\_test), 112

day (auxi.core.time.TimePeriod attribute), 60

description (auxi.modelling.process.materials.thermo.Material G (in module auxi.tools.chemistry.thermochemistry.Compound method), 106

formula (auxi.tools.chemistry.thermochemistry.Compound attribute), 106



G() (auxi.tools.chemistry.thermochemistry.Phaseget\_assay\_total()  
method), 108 (auxi.modelling.process.materials.slurry.Material  
G() (in module method), 93  
auxi.tools.chemistry.thermochemistry), get\_assay\_total()  
107 (auxi.modelling.process.materials.thermo.Material  
gas (auxi.tools.materialphysicalproperties.core.StateOfMatter  
attribute), 112 get\_child\_account()  
gas\_plasma (auxi.tools.materialphysicalproperties.core.StateOfMatter  
attribute), 112 method), 74  
GeneralLedger (class in get\_component()  
auxi.modelling.financial.des), 72 (auxi.modelling.business.structure.Component  
GeneralLedgerAccount (class in method), 68  
auxi.modelling.financial.des), 74 get\_compound\_amount()  
GeneralLedgerAccountUnitTester (class in (auxi.modelling.process.materials.thermo.MaterialPa  
auxi.modelling.financial.des\_test), 77 method), 99  
GeneralLedgerStructure (class in get\_compound\_amounts()  
auxi.modelling.financial.des), 75 (auxi.modelling.process.materials.thermo.MaterialPa  
GeneralLedgerStructure (class in method), 99  
auxi.modelling.financial.reporting), get\_compound\_index()  
78 (auxi.modelling.process.materials.chem.Material  
GeneralLedgerStructureUnitTester (class in method), 82  
auxi.modelling.financial.des\_test), 77 get\_compound\_index()  
GeneralLedgerStructureUnitTester (class in (auxi.modelling.process.materials.thermo.Material  
auxi.modelling.financial.reporting\_test), method), 97  
80 get\_compound\_mass()  
GeneralLedgerUnitTester (class in (auxi.modelling.process.materials.chem.MaterialPac  
auxi.modelling.financial.des\_test), 77 method), 83  
get\_account() (auxi.modelling.financial.des.GeneralLedgerStructure  
method), 75 (auxi.modelling.process.materials.thermo.MaterialPa  
get\_account\_decendants() method), 99  
(auxi.modelling.financial.des.GeneralLedgerStructure  
method), 75 (auxi.modelling.process.materials.chem.MaterialPac  
get\_activity() (auxi.modelling.business.structure.Component  
method), 68 get\_datafile\_references() (in module  
get\_assay() (auxi.modelling.process.materials.chem.MaterialPackage  
method), 83 109  
get\_assay() (auxi.modelling.process.materials.psd.MaterialPackage  
method), 89 get\_datetime() (auxi.core.time.Clock  
get\_assay() (auxi.modelling.process.materials.slurry.MaterialPackage  
method), 94 get\_datetime\_at\_period\_ix()  
get\_assay() (auxi.modelling.process.materials.thermo.MaterialPackage  
method), 99 60  
get\_assay\_total() get\_density() (auxi.modelling.process.materials.slurry.Materi  
(auxi.modelling.process.materials.chem.Material  
method), 82 get\_element\_mass()  
get\_assay\_total() (auxi.modelling.process.materials.chem.MaterialPac  
(auxi.modelling.process.materials.psd.Material method), 84  
method), 88 get\_element\_mass()

(auxi.modelling.process.materials.thermo.MaterialPackage  
method), 99  
get\_element\_mass\_dictionary() (auxi.modelling.process.materials.slurry.MaterialPackage  
(auxi.modelling.process.materials.chem.MaterialPackage  
method), 84  
get\_element\_mass\_dictionary() (auxi.modelling.process.materials.psd.MaterialPackage  
(auxi.modelling.process.materials.thermo.MaterialPackage  
method), 99  
get\_element\_masses() (auxi.modelling.process.materials.slurry.MaterialPackage  
(auxi.modelling.process.materials.chem.MaterialPackage  
method), 84  
get\_element\_masses() (auxi.modelling.process.materials.slurry.MaterialPackage  
(auxi.modelling.process.materials.thermo.MaterialPackage  
method), 100  
get\_mass() (auxi.modelling.process.materials.chem.MaterialPackage  
method), 84  
get\_mass() (auxi.modelling.process.materials.psd.MaterialPackage  
method), 89  
get\_mass() (auxi.modelling.process.materials.slurry.MaterialPackage  
method), 94  
get\_mass\_fraction\_solids() (auxi.modelling.process.materials.slurry.MaterialPackage  
method), 94  
get\_path\_relative\_to\_module() (in module H (auxi.modelling.process.materials.thermo.MaterialPackage  
auxi.core.helpers), 57  
get\_phase\_list() h (in module auxi.tools.physicalconstants),  
(auxi.tools.chemistry.thermochemistry.Compound  
method), 106  
get\_reference() H() (auxi.tools.chemistry.thermochemistry.Compound  
method), 106  
get\_referenced\_accounts() H() (auxi.tools.chemistry.thermochemistry.CpRecord  
method), 107  
get\_referenced\_accounts() H() (auxi.tools.chemistry.thermochemistry.Phase  
method), 108  
get\_referenced\_accounts() (in module auxi.tools.chemistry.thermochemistry),  
(auxi.modelling.business.basic.BasicLoanActivity  
method), 63  
get\_referenced\_accounts() h\_bar (in module  
auxi.tools.physicalconstants), 123  
get\_referenced\_accounts() (auxi.modelling.business.structure.ActivityHelpersUnitTester (class in  
method), 67 auxi.core.helpers\_test), 57  
get\_size\_class\_index() hour (auxi.core.time.TimePeriod attribute), 60  
(auxi.modelling.process.materials.psd.Material  
method), 88  
get\_size\_class\_index() income\_statement  
(auxi.modelling.process.materials.slurry.Material  
attribute), 79  
method), 93  
get\_size\_class\_mass() income\_statement()  
(auxi.modelling.process.materials.psd.MaterialPackage  
method), 73

IncomeStatement	(class in Material	(class in
auxi.modelling.financial.reporting),	auxi.modelling.process.materials.chem),	
78	81	
interest_rate (auxi.modelling.business.basic.BasicMaterial	Activity	(class in
attribute), 63	auxi.modelling.process.materials.core),	
	85	
<b>K</b>	Material	(class in
k() (auxi.modelling.process.materials.core.Material	auxi.modelling.process.materials.psd),	
method), 86	87	
k_B (in module auxi.tools.physicalconstants),	Material	(class in
123	auxi.modelling.process.materials.slurry),	
	91	
<b>L</b>	Material	(class in
latex (auxi.core.reporting.ReportFormat at-	auxi.modelling.process.materials.thermo),	
tribute), 59	96	
liability (auxi.modelling.financial.des.AccountType	MaterialPackage	(class in
attribute), 72	auxi.modelling.process.materials.chem),	
liquid (auxi.tools.materialphysicalproperties.core.StateOfMatter		
attribute), 112	MaterialPackage	(class in
liquid_gas_plasma	auxi.modelling.process.materials.psd),	
(auxi.tools.materialphysicalproperties.core.StateOfMatter		
attribute), 112	MaterialPackage	(class in
liquid_plasma (auxi.tools.materialphysicalproperties.core.StateOfMatter	auxi.modelling.process.materials.slurry),	
attribute), 112	93	
list_compounds() (in module	MaterialPackage	(class in
auxi.tools.chemistry.thermochemistry),	auxi.modelling.process.materials.thermo),	
109	98	
load_data_auxi() (in module	MaterialTester	(class in
auxi.tools.chemistry.thermochemistry),	auxi.modelling.process.materials.core_test),	
109	87	
load_data_factsage() (in module	matplotlib (auxi.core.reporting.ReportFormat	
auxi.tools.chemistry.thermochemistry),	attribute), 59	
109	millisecond (auxi.core.time.TimePeriod at-	
	tribute), 60	
<b>M</b>	minute (auxi.core.time.TimePeriod attribute),	
m_u (in module auxi.tools.physicalconstants),	60	
123	mm (auxi.tools.materialphysicalproperties.idealgas.RhoT	
mass (auxi.modelling.process.materials.thermo.MaterialPackage	attribute), 114	
attribute), 100	mm (auxi.tools.materialphysicalproperties.idealgas.RhoTP	
mass() (in module	attribute), 114	
auxi.tools.chemistry.stoichiometry),	Model	(class in
104	auxi.tools.materialphysicalproperties.core),	
mass_fractions() (in module	111	
auxi.tools.chemistry.stoichiometry),	molar_mass (auxi.tools.chemistry.thermochemistry.Compound	
104	attribute), 107	
masses() (in module	molar_mass() (in module	
auxi.tools.chemistry.stoichiometry),	auxi.tools.chemistry.stoichiometry),	
104	104	

molar\_mass() (in module Phase (class in  
 auxi.tools.chemistry.thermochemistry),  
 109  
 108  
 month (auxi.core.time.TimePeriod attribute), plasma (auxi.tools.materialphysicalproperties.core.StateOfMa  
 60 attribute), 112  
 mstate (auxi.modelling.process.materials.core.Material (auxi.tools.materialphysicalproperties.polynomial.Poly  
 attribute), 86 method), 117  
 mu() (auxi.modelling.process.materials.core.Material (auxi.core.reporting.ReportFormat at-  
 tribute), 59  
 method), 86  
**N** PolynomialModelT (class in  
 auxi.tools.materialphysicalproperties.polynomial),  
 N\_A (in module auxi.tools.physicalconstants), 116  
 123  
 PolynomialModelTTester (class in  
 name (auxi.core.objects.NamedObject at- auxi.tools.materialphysicalproperties.polynomial\_test  
 tribute), 58 117  
 name (auxi.modelling.business.models.TimeBasedModel (in module  
 attribute), 66 auxi.tools.transportphenomena.dimensionlessquantity  
 name (auxi.modelling.business.structure.Activity 121  
 attribute), 67 prepare\_to\_run()  
 name (auxi.modelling.business.structure.Component (auxi.modelling.business.basic.BasicLoanActivity  
 attribute), 68 method), 63  
 name (auxi.modelling.business.structure.Entity prepare\_to\_run()  
 attribute), 69 (auxi.modelling.business.models.TimeBasedModel  
 name (auxi.modelling.financial.des.GeneralLedgerAccount method), 66  
 attribute), 75 prepare\_to\_run()  
 name (auxi.modelling.process.materials.thermo.Material (auxi.modelling.business.structure.Activity  
 attribute), 98 method), 67  
 name (auxi.tools.chemistry.thermochemistry.Phase prepare\_to\_run()  
 attribute), 109 (auxi.modelling.business.structure.Component  
 method), 68  
 NamedObject (class in auxi.core.objects), 58  
 NamedObjectUnitTester (class in prepare\_to\_run()  
 auxi.core.objects\_test), 58 (auxi.modelling.business.structure.Entity  
 nu() (auxi.modelling.process.materials.core.Material method), 69  
 method), 86  
 Nu() (in module printout (auxi.core.reporting.ReportFormat at-  
 auxi.tools.transportphenomena.dimensionlessquantityPackageUnitTester (class in  
 120 auxi.modelling.process.materials.psd\_test),  
 90  
**O** PsdMaterialUnitTester (class in  
 Object (class in auxi.core.objects), 58 auxi.modelling.process.materials.psd\_test),  
 ObjectUnitTester (class in 91  
 auxi.core.objects\_test), 58  
**P** **R**  
 P (auxi.modelling.process.materials.thermo.MaterialPackage  
 attribute), 98  
 Ra() (in module  
 P (auxi.tools.materialphysicalproperties.idealgas.RhoT auxi.tools.transportphenomena.dimensionlessquantity  
 attribute), 113 121

raw\_assays (auxi.modelling.process.materials.thermo.MaterialTools.materialphysicalproperties.idealgas),  
 attribute), 98 114

Re() (in module RhoTPxTester (class in  
 auxi.tools.transportphenomena.dimensionlessquantities).materialphysicalproperties.idealgas\_test),  
 122 115

read() (auxi.core.objects.Object method), 58 RhoTTester (class in  
 remove\_account() auxi.tools.materialphysicalproperties.idealgas\_test),  
 (auxi.modelling.financial.des.GeneralLedgerAccount  
 method), 75 RiboudViscosityTx (class in  
 remove\_component() auxi.tools.materialphysicalproperties.slags),  
 (auxi.modelling.business.structure.Component 118  
 method), 68 RiboudViscosityTy (class in  
 remove\_component() auxi.tools.materialphysicalproperties.slags),  
 (auxi.modelling.business.structure.Entity 118  
 method), 69 run() (auxi.modelling.business.basic.BasicActivity  
 remove\_entity() method), 62  
 (auxi.modelling.business.models.TimeBasedModel  
 method), 66 run() (auxi.modelling.business.basic.BasicLoanActivity  
 method), 64

render() (auxi.core.reporting.Report method), 59 run() (auxi.modelling.business.models.TimeBasedModel  
 method), 66

Report (class in auxi.core.reporting), 59 run() (auxi.modelling.business.structure.Component  
 method), 68

Report (class in auxi.modelling.financial.reporting), 79 run() (auxi.modelling.business.structure.Entity  
 method), 70

report() (auxi.modelling.financial.des.GeneralLedgerStructure  
 method), 75

ReportFormat (class in auxi.core.reporting), 59 S() (auxi.tools.chemistry.thermochemistry.Compound  
 method), 106

ReportingUnitTester (class in auxi.core.reporting\_test), 59 S() (auxi.tools.chemistry.thermochemistry.CpRecord  
 method), 107

ReportType (class in auxi.modelling.financial.reporting), 79 S() (auxi.tools.chemistry.thermochemistry.Phase  
 method), 108

reset() (auxi.core.time.Clock method), 60 S() (in module  
 auxi.tools.chemistry.thermochemistry),  
 revenue (auxi.modelling.financial.des.AccountType 109  
 attribute), 72 second (auxi.core.time.TimePeriod attribute),  
 rho() (auxi.modelling.process.materials.core.Material 60  
 method), 86 set\_parent\_path()

RhoT (class in (auxi.modelling.business.structure.Activity  
 auxi.tools.materialphysicalproperties.idealgas), method), 67  
 113 set\_parent\_path()

RhoTP (class in (auxi.modelling.business.structure.Component  
 auxi.tools.materialphysicalproperties.idealgas), method), 69  
 114 set\_parent\_path()

RhoTPTester (class in (auxi.modelling.business.structure.Entity  
 auxi.tools.materialphysicalproperties.idealgas\_test), method), 70  
 115 set\_parent\_path()

RhoTPx (class in (auxi.modelling.financial.des.GeneralLedgerAccount



[illegible]

## T

	test__str__() (auxi.core.objects_test.NamedObjectUnitTester method), 58
T (auxi.modelling.process.materials.thermo.MaterialPackage attribute), 98	test_add_activity_invalid_account_name() (auxi.modelling.business.structure_test.ComponentUnitTester method), 70
tearDown() (auxi.core.objects_test.NamedObjectUnitTester method), 58	test_add_activity_valid_account_name() (auxi.modelling.business.structure_test.ComponentUnitTester method), 70
tearDown() (auxi.core.objects_test.ObjectUnitTester method), 59	test_add_assay() (auxi.modelling.process.materials.chem_test.ChemMaterUnitTester method), 85
tearDown() (auxi.core.reporting_test.ReportingUnitTester method), 60	test_add_assay() (auxi.modelling.process.materials.slurry_test.SlurryMaterialPackageUnitTester method), 91
test__str__() (auxi.core.objects_test.ObjectUnitTester method), 59	test_add_assay() (auxi.modelling.process.materials.psd_test.PsdMaterialPackageUnitTester method), 91
test__str__() (auxi.modelling.process.materials.slurry_test.SlurryMaterialPackageUnitTester method), 95	test_add_assay() (auxi.modelling.process.materials.psd_test.PsdMaterialPackageUnitTester method), 91
test__str__() (auxi.modelling.process.materials.thermo_test.ThermoMaterialPackageUnitTester method), 100	test_add_operator_1() (auxi.modelling.process.materials.slurry_test.SlurryMaterialPackageUnitTester method), 95
test__generate_table_() (auxi.modelling.financial.reporting_test.GeneralLedgerStructureUnitTester method), 80	test_add_operator_1() (auxi.modelling.process.materials.thermo_test.ThermoMaterialPackageUnitTester method), 101
test__generate_table_() (auxi.modelling.financial.reporting_test.TransactionListUnitTester method), 80	test_add_operator_1() (auxi.modelling.process.materials.chem_test.ChemMaterialPackageUnitTester method), 84
test__meet_exection_criteria() (auxi.modelling.business.basic_test.BasicActivityUnitTester method), 64	test_add_operator_1() (auxi.modelling.process.materials.psd_test.PsdMaterialPackageUnitTester method), 90
test__meet_exection_criteria() (auxi.modelling.business.basic_test.BasicLoanActivityUnitTester method), 64	test_add_operator_1() (auxi.modelling.process.materials.slurry_test.SlurryMaterialPackageUnitTester method), 95
test__meet_exection_criteria() (auxi.modelling.business.structure_test.ActivityUnitTester method), 70	test_add_operator_1() (auxi.modelling.process.materials.thermo_test.ThermoMaterialPackageUnitTester method), 100
test__perform_year_end_gross_profit() (auxi.modelling.business.structure_test.EntityUnitTester method), 71	test_add_operator_2() (auxi.modelling.process.materials.chem_test.ChemMaterialPackageUnitTester method), 84
test__perform_year_end_gross_profit_and_income_summary() (auxi.modelling.business.structure_test.EntityUnitTester method), 71	test_add_operator_2() (auxi.modelling.process.materials.thermo_test.ThermoMaterialPackageUnitTester method), 100
test__perform_year_end_income_summary() (auxi.modelling.business.structure_test.EntityUnitTester method), 71	test_add_operator_3() (auxi.modelling.process.materials.chem_test.ChemMaterialPackageUnitTester method), 84
test__perform_year_end_income_tax() (auxi.modelling.business.structure_test.EntityUnitTester method), 71	test_add_operator_3() (auxi.modelling.process.materials.psd_test.PsdMaterialPackageUnitTester method), 90
test__perform_year_end_procedure() (auxi.modelling.business.structure_test.EntityUnitTester method), 71	test_add_operator_3() (auxi.modelling.process.materials.slurry_test.SlurryMaterialPackageUnitTester method), 95
test__perform_year_end_retained_earnings() (auxi.modelling.business.structure_test.EntityUnitTester method), 71	test_add_operator_3() (auxi.modelling.process.materials.slurry_test.SlurryMaterialPackageUnitTester method), 95

[illegible]



test\_constructor() method), 71  
 (auxi.modelling.process.materials.chem\_test.ChemMaterialUnitTester  
 method), 85 (auxi.modelling.process.materials.chem\_test.ChemM  
 test\_constructor() method), 85  
 (auxi.modelling.process.materials.core\_test.MaterialTester assay()  
 method), 87 (auxi.modelling.process.materials.psd\_test.PsdMater  
 test\_constructor() method), 91  
 (auxi.modelling.process.materials.psd\_test.PsdMaterialPackageUnitTester  
 method), 90 (auxi.modelling.process.materials.slurry\_test.SlurryM  
 test\_constructor() method), 95  
 (auxi.modelling.process.materials.psd\_test.PsdMaterialUnitTester)  
 method), 91 (auxi.modelling.process.materials.thermo\_test.Therm  
 test\_constructor() method), 101  
 (auxi.modelling.process.materials.slurry\_test.SlurryMaterialPackageUnitTester  
 method), 95 (auxi.modelling.business.models\_test.TimeBasedMo  
 test\_constructor() method), 66  
 (auxi.modelling.process.materials.slurry\_test.SlurryMaterialUnitTester  
 method), 95 (auxi.modelling.process.materials.chem\_test.ChemM  
 test\_constructor() method), 85  
 (auxi.modelling.process.materials.thermo\_test.ThermoMaterialPackageUnitTester  
 method), 100 (auxi.modelling.process.materials.psd\_test.PsdMater  
 test\_constructor() method), 91  
 (auxi.modelling.process.materials.thermo\_test.ThermoMaterialUnitTester  
 method), 101 (auxi.modelling.process.materials.slurry\_test.SlurryM  
 test\_convert\_compound() method), 95  
 (auxi.tools.chemistry.stoichiometry\_test.StoichFuncPackTester)  
 method), 105 (auxi.modelling.process.materials.thermo\_test.Therm  
 test\_Cp() (auxi.tools.chemistry.thermochemistry\_test.ThermoFunctionTester  
 method), 110 test\_create\_template()  
 test\_cpRecord\_\_str\_\_() (auxi.tools.materialphysicalproperties.core\_test.Data  
 (auxi.tools.chemistry.thermochemistry\_test.ThermoFunctionTester  
 method), 110 test\_create\_transaction()  
 test\_create() (auxi.tools.materialphysicalproperties.ideal\_gas\_test.RhoTPTester  
 method), 115 (auxi.modelling.financial.des\_test.GeneralLedgerUni  
 test\_create() (auxi.tools.materialphysicalproperties.ideal\_gas\_test.RhoTPxTester  
 method), 115 (auxi.tools.materialphysicalproperties.core\_test.Data  
 test\_create() (auxi.tools.materialphysicalproperties.ideal\_gas\_test.RhoTTTester  
 method), 116 test\_element\_mass\_fraction()  
 test\_create() (auxi.tools.materialphysicalproperties.polynomial\_test.PolynomialModelTester  
 method), 117 (auxi.tools.chemistry.stoichiometry\_test.StoichFunc  
 test\_create\_account() test\_element\_mass\_fractions()  
 (auxi.modelling.financial.des\_test.GeneralLedgerAccountUnitTester  
 method), 77 (auxi.modelling.business.chemistry.stoichiometry\_test.StoichFunc  
 test\_create\_component() test\_elements()  
 (auxi.modelling.business.structure\_test.ComponentUnitTester  
 method), 70 (auxi.modelling.business.chemistry.stoichiometry\_test.StoichFunc  
 test\_create\_component() test\_extract\_1()  
 (auxi.modelling.business.structure\_test.EntityUnitTester  
 (auxi.modelling.process.materials.chem\_test.ChemM

method), 85	test_get_assay_total()
test_extract_1()	(auxi.modelling.process.materials.slurry_test.SlurryTestMaterialPackageUnitTester
(auxi.modelling.process.materials.psd_test.PsdMaterialPackageUnitTester	method), 90
test_extract_1()	test_get_assay_total()
(auxi.modelling.process.materials.slurry_test.SlurryTestMaterialPackageUnitTester	method), 95
test_extract_1()	test_get_child_account()
(auxi.modelling.financial.des_test.GeneralLedgerAccountMaterialPackageUnitTester	method), 75
test_extract_2()	test_get_component_exists()
(auxi.modelling.business.structure_test.ComponentUnitMaterialPackageUnitTester	method), 100
test_extract_2()	test_get_component_not_exists()
(auxi.modelling.business.structure_test.ComponentUnitMaterialPackageUnitTester	method), 100
test_extract_3()	test_get_compound_index()
(auxi.modelling.process.materials.thermo_test.ThermoMaterialPackageUnitTester	method), 100
test_G() (auxi.tools.chemistry.thermochemistry_test.ThermoModelingTester	method), 110
test_get_account()	test_get_compound_index()
(auxi.modelling.financial.des_test.GeneralLedgerAccountMaterialPackageUnitTester	method), 77
test_get_account_descendants()	test_get_compound_mass()
(auxi.modelling.financial.des_test.GeneralLedgerAccountMaterialPackageUnitTester	method), 77
test_get_activity_exists()	test_get_compound_mass()
(auxi.modelling.business.structure_test.ComponentUnitMaterialPackageUnitTester	method), 70
test_get_activity_not_exists()	test_get_datafile_references()
(auxi.modelling.business.structure_test.ComponentUnitMaterialPackageUnitTester	method), 70
test_get_assay()	test_get_date()
(auxi.modelling.process.materials.chem_test.ChemMaterialPackageUnitTester	method), 85
test_get_assay()	test_get_datetime()
(auxi.modelling.process.materials.psd_test.PsdMaterialPackageUnitTester	method), 90
test_get_assay()	test_get_datetime_at_period_ix()
(auxi.modelling.process.materials.slurry_test.SlurryTestMaterialPackageUnitTester	method), 95
test_get_assay()	test_get_element_masses()
(auxi.modelling.process.materials.thermo_test.ThermoMaterialPackageUnitTester	method), 101
test_get_assay_total()	test_get_element_masses()
(auxi.modelling.process.materials.chem_test.ChemMaterialPackageUnitTester	method), 85
test_get_assay_total()	test_get_H() (auxi.modelling.process.materials.thermo_test.ThermoModelingTester
(auxi.modelling.process.materials.psd_test.PsdMaterialPackageUnitTester	method), 91
	test_get_mass()

(auxi.modelling.process.materials.chem\_test.ChemMaterialPackageUnitTester  
 method), 85

test\_invalid\_characters() (auxi.modelling.process.materials.psd\_test.PsdMaterialPackageUnitTester  
 method), 90

test\_load\_data\_auxi() (auxi.modelling.process.materials.slurry\_test.SlurryMaterialPackageUnitTester  
 method), 95

test\_get\_P() (auxi.modelling.process.materials.thermo\_test.ThermoMaterialPackageUnitTester  
 method), 101

test\_get\_path() (auxi.modelling.business.structure\_test.ActivityUnitTester  
 method), 70

test\_get\_path\_relative\_to\_module() (auxi.core.helpers\_test.HelpersUnitTester  
 method), 58

test\_get\_reference() (auxi.tools.chemistry.thermochemistry\_test.ThermochemistryUnitTester  
 method), 110

test\_get\_referenced\_accounts() (auxi.modelling.business.basic\_test.BasicActivityUnitTester  
 method), 64

test\_get\_referenced\_accounts() (auxi.modelling.business.basic\_test.BasicLoanActivityUnitTester  
 method), 65

test\_get\_referenced\_accounts() (auxi.modelling.business.structure\_test.ActivityUnitTester  
 method), 70

test\_get\_size\_class\_index() (auxi.modelling.process.materials.psd\_test.PsdMaterialPackageUnitTester  
 method), 91

test\_get\_size\_class\_index() (auxi.modelling.process.materials.slurry\_test.SlurryMaterialPackageUnitTester  
 method), 95

test\_get\_size\_class\_mass() (auxi.modelling.process.materials.psd\_test.PsdMaterialPackageUnitTester  
 method), 90

test\_get\_size\_class\_mass() (auxi.modelling.process.materials.slurry\_test.SlurryMaterialPackageUnitTester  
 method), 95

test\_get\_T() (auxi.modelling.process.materials.thermo\_test.ThermoMaterialPackageUnitTester  
 method), 101

test\_getitem\_exists() (auxi.modelling.business.structure\_test.EntityUnitTester  
 method), 71

test\_getitem\_not\_exists() (auxi.modelling.business.structure\_test.EntityUnitTester  
 method), 71

test\_invalid\_characters() (auxi.modelling.process.materials.psd\_test.PsdMaterialPackageUnitTester  
 method), 105

test\_load\_data\_auxi() (auxi.modelling.process.materials.slurry\_test.SlurryMaterialPackageUnitTester  
 method), 110

test\_mass() (auxi.tools.chemistry.stoichiometry\_test.StoichiometryUnitTester  
 method), 105

test\_material() (auxi.tools.materialphysicalproperties.core\_test.DataUnitTester  
 method), 112

test\_molar\_mass() (auxi.tools.chemistry.stoichiometry\_test.StoichiometryUnitTester  
 method), 105

test\_molar\_mass() (auxi.tools.chemistry.thermochemistry\_test.ThermochemistryUnitTester  
 method), 110

test\_multiply\_operator() (auxi.modelling.process.materials.chem\_test.ChemMaterialPackageUnitTester  
 method), 85

test\_multiply\_operator() (auxi.modelling.process.materials.psd\_test.PsdMaterialPackageUnitTester  
 method), 90

test\_multiply\_operator() (auxi.modelling.process.materials.slurry\_test.SlurryMaterialPackageUnitTester  
 method), 95

test\_multiply\_operator() (auxi.modelling.process.materials.thermo\_test.ThermoMaterialPackageUnitTester  
 method), 101

test\_name() (auxi.tools.materialphysicalproperties.core\_test.DataUnitTester  
 method), 112

test\_parameter\_units() (auxi.tools.chemistry.thermochemistry\_test.ThermochemistryUnitTester  
 method), 113

test\_phase\_\_str\_\_() (auxi.tools.chemistry.thermochemistry\_test.ThermochemistryUnitTester  
 method), 110

test\_plot() (auxi.tools.materialphysicalproperties.polynomial\_test.PolynomialUnitTester  
 method), 113

method), 117	test_run_first_month()
test_prepare_to_run()	(auxi.modelling.business.basic_test.BasicLoanActivi
(auxi.modelling.business.models_test.TimeBasedModelUnit	method), 66
method), 66	test_run_last_month()
test_prepare_to_run()	(auxi.modelling.business.basic_test.BasicLoanActivi
(auxi.modelling.business.structure_test.ActivityUnitTeste	method), 70
method), 70	test_run_third_month()
test_prepare_to_run()	(auxi.modelling.business.basic_test.BasicLoanActivi
(auxi.modelling.business.structure_test.ComponentUnitTeste	method), 71
method), 71	test_S() (auxi.tools.chemistry.thermochemistry_test.ThermoF
test_prepare_to_run()	method), 110
(auxi.modelling.business.structure_test.EntityUnitTeste	method), 71
method), 71	method), 101
test_read() (auxi.tools.materialphysicalproperties.polynomial	test_polynomial_test.PolynomialModelTTester
method), 118	(auxi.modelling.business.models_test.TimeBasedMo
test_reference()	method), 66
(auxi.tools.materialphysicalproperties.core_test.DataSe	test_test_DataSe)Tester
method), 113	(auxi.modelling.business.structure_test.ActivityUnitT
test_remove_account()	method), 70
(auxi.modelling.financial.des_test.GeneralLedgerAccount	test_ledger_account)UnitTester
method), 77	(auxi.modelling.business.structure_test.ComponentU
test_remove_component()	method), 71
(auxi.modelling.business.structure_test.ComponentUnit	method), 71
method), 71	(auxi.modelling.business.structure_test.EntityUnitTe
test_remove_component()	method), 72
(auxi.modelling.business.structure_test.EntityUnitTeste	test_entity_testerpath()
method), 71	(auxi.modelling.business.structure_test.ActivityUnitT
test_remove_entity()	method), 70
(auxi.modelling.business.models_test.TimeBasedModelUnit	test_time_based_model_path)TTester
method), 66	(auxi.modelling.business.structure_test.ComponentU
test_render_with_file()	method), 71
(auxi.core.reporting_test.ReportingUnitTester	test_reporter_parent_path()
method), 60	(auxi.modelling.business.structure_test.EntityUnitTe
test_render_without_file()	method), 72
(auxi.core.reporting_test.ReportingUnitTester	test_reporter_parent_path()
method), 60	(auxi.modelling.financial.des_test.GeneralLedgerAcco
test_report() (auxi.modelling.financial.des_test.GeneralLedgerStructureUnitTester	method), 77
method), 77	test_set_T() (auxi.modelling.process.materials.thermo_test.TI
test_reset() (auxi.core.time_test.ClockUnitTester	method), 101
method), 61	test_stoichiometry_coefficient()
test_run() (auxi.modelling.business.basic_test.BasicActivi	test_stoichiometry_chemistry.stoichiometry_test.StoichFunc
method), 64	method), 105
test_run() (auxi.modelling.business.models_test.TimeBasedModelUnitTester	test_time_based_model_unit_tester
method), 66	(auxi.tools.chemistry.stoichiometry_test.StoichFunc
test_run() (auxi.modelling.business.structure_test.ComponentUnitTester	method), 71
method), 71	test_subtract_operator_2()
test_run() (auxi.modelling.business.structure_test.EntityUnitTester	test_subtract_operator_2)
method), 71	method), 85

test\_subtract\_operator\_2() (auxi.modelling.process.materials.psd\_test.PsdMaterialPackagingUnitTester method), 90

test\_subtract\_operator\_2() (auxi.modelling.process.materials.slurry\_test.SlurryMaterialPackagingUnitTester method), 95

test\_subtract\_operator\_3() (auxi.modelling.process.materials.chem\_test.ChemMaterialPackagingUnitTester method), 85

test\_subtract\_operator\_3() (auxi.modelling.process.materials.psd\_test.PsdMaterialPackagingUnitTester method), 91

test\_subtract\_operator\_3() (auxi.modelling.process.materials.slurry\_test.SlurryMaterialPackagingUnitTester method), 95

test\_tick() (auxi.core.time\_test.ClockUnitTester method), 61

test\_validate\_account\_name\_invalid() (auxi.modelling.financial.des\_test.GeneralLedgerStructureUnitTester method), 77

test\_validate\_account\_name\_valid() (auxi.modelling.financial.des\_test.GeneralLedgerStructureUnitTester method), 77

test\_write() (auxi.tools.materialphysicalproperties.polynomial\_test.PolynomialModelTTTester method), 118

ThermoFunctionTester (class in auxi.tools.chemistry.thermochemistry\_test), 110

ThermoMaterialPackageUnitTester (class in auxi.modelling.process.materials.thermo\_test), 100

ThermoMaterialUnitTester (class in auxi.modelling.process.materials.thermo\_test), 101

tick() (auxi.core.time.Clock method), 60

TimeBasedModel (class in auxi.modelling.business.models), 65

TimeBasedModelUnitTester (class in auxi.modelling.business.models\_test), 66

TimePeriod (class in auxi.core.time), 60

Tmax (auxi.tools.chemistry.thermochemistry.CpRecord attribute), 107

Tmin (auxi.tools.chemistry.thermochemistry.CpRecord attribute), 107

Transaction (class in auxi.modelling.financial.des), 76

transaction\_list (auxi.modelling.financial.des.GeneralLedgerStructure attribute), 79

transaction\_list() (auxi.modelling.financial.des.GeneralLedgerStructure attribute), 79

TransactionList (class in auxi.modelling.financial.des.GeneralLedgerStructure), 79

TransactionListUnitTester (class in auxi.modelling.financial.des.GeneralLedgerStructure\_test), 80

TransactionTemplate (class in auxi.modelling.financial.des.GeneralLedgerStructure), 76

TransactionTemplateUnitTester (class in auxi.modelling.financial.des.GeneralLedgerStructure\_test), 77

TransactionUnitTester (class in auxi.modelling.financial.des.GeneralLedgerStructure\_test), 78

UnitTester (class in auxi.tools.chemistry.thermochemistry\_test), 109

txt (auxi.core.reporting.ReportFormat attribute), 59

U

unknown (auxi.tools.materialphysicalproperties.core.StateOfMatter attribute), 112

UrbanViscosityTx (class in auxi.tools.materialphysicalproperties.slags), 118

UrbanViscosityTy (class in auxi.tools.materialphysicalproperties.slags), 119

V

validate\_account\_names() (auxi.modelling.financial.des.GeneralLedgerStructure method), 75

W

week (auxi.core.time.TimePeriod attribute), 61

write() (auxi.core.objects.Object method), 58

write\_compound\_to\_auxi\_file() (in module auxi.tools.chemistry.thermochemistry), 109

Y

year (auxi.core.time.TimePeriod attribute), 61